
COM/Automation User Guide and Reference Manual

Version 7.0



Copyright and Trademarks

LispWorks COM/Automation User Guide and Reference Manual

Version 7.0

February 2015

Copyright © 2015 by LispWorks Ltd.

All Rights Reserved. No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of LispWorks Ltd.

The information in this publication is provided for information only, is subject to change without notice, and should not be construed as a commitment by LispWorks Ltd. LispWorks Ltd assumes no responsibility or liability for any errors or inaccuracies that may appear in this publication. The software described in this book is furnished under license and may only be used or copied in accordance with the terms of that license.

LispWorks and KnowledgeWorks are registered trademarks of LispWorks Ltd.

Adobe and PostScript are registered trademarks of Adobe Systems Incorporated. Other brand or product names are the registered trademarks or trademarks of their respective holders.

The code for `walker.lisp` and `compute-combination-points` is excerpted with permission from PCL, Copyright © 1985, 1986, 1987, 1988 Xerox Corporation.

The XP Pretty Printer bears the following copyright notice, which applies to the parts of LispWorks derived therefrom:

Copyright © 1989 by the Massachusetts Institute of Technology, Cambridge, Massachusetts.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that this copyright and permission notice appear in all copies and supporting documentation, and that the name of M.I.T. not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. M.I.T. makes no representation about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty. M.I.T. disclaims all warranties with regard to this software, including all implied warranties of merchantability and fitness. In no event shall M.I.T. be liable for any special, indirect or consequential damages or any damages whatsoever resulting from loss of use, data or profits, whether in an action of contract, negligence or other tortious action, arising out of or in connection with the use or performance of this software.

LispWorks contains part of ICU software obtained from <http://source.icu-project.org> and which bears the following copyright and permission notice:

ICU License - ICU 1.8.1 and later

COPYRIGHT AND PERMISSION NOTICE

Copyright © 1995-2006 International Business Machines Corporation and others. All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder. All trademarks and registered trademarks mentioned herein are the property of their respective owners.

US Government Restricted Rights

The LispWorks Software is a commercial computer software program developed at private expense and is provided with restricted rights. The LispWorks Software may not be used, reproduced, or disclosed by the Government except as set forth in the accompanying End User License Agreement and as provided in DFARS 227.7202-1(a), 227.7202-3(a) (1995), FAR 12.212(a)(1995), FAR 52.227-19, and/or FAR 52.227-14 Alt III, as applicable. Rights reserved under the copyright laws of the United States.

Address

LispWorks Ltd
St. John's Innovation Centre
Cowley Road
Cambridge
CB4 0WS
England

Telephone

From North America: 877 759 8839
(toll-free)
From elsewhere: +44 1223 421860

Fax

From North America: 617 812 8283
From elsewhere: +44 870 2206189

www.lispworks.com

Contents

Preface vii

1 Using COM 1

Prerequisites 1

Including COM in a Lisp application 1

The mapping from COM names to Lisp symbols 3

Obtaining the first COM interface pointer 3

Reference counting 4

Querying for other COM interface pointers 4

Calling COM interface methods 4

Implementing COM interfaces in Lisp 13

Calling COM object methods from Lisp 24

2 COM Reference Entries 27

add-ref 27

automation-server-command-line-action 28

automation-server-main 29

automation-server-top-loop 32

call-com-interface 33

call-com-object 35

check-hresult 36

co-create-guid 37

co-initialize 38

co-task-mem-alloc 38

co-task-mem-free 40

co-uninitialize 40
com-error 41
com-interface 42
com-interface-refguid 42
com-object 43
com-object-destructor 43
com-object-from-pointer 44
com-object-initialize 45
com-object-query-interface 46
create-instance 47
define-com-implementation 48
define-com-method 51
find-clsid 53
get-object 54
guid-equal 55
guid-to-string 56
hresult 56
hresult-equal 57
i-unknown 57
interface-ref 58
make-factory-entry 59
make-guid-from-string 60
midl 61
midl-default-import-paths 64
midl-set-import-paths 65
:midl-file 65
query-interface 66
query-object-interface 67
refguid 68
refguid-interface-name 69
refiid 69
register-class-factory-entry 70
register-server 71
release 72
s_ok 73
server-can-exit-p 74
server-in-use-p 74
set-automation-server-exit-delay 75
set-register-server-error-reporter 75
standard-i-unknown 77

- start-factories 78
- stop-factories 79
- succeeded 79
- unregister-server 80
- with-com-interface 81
- with-com-object 83
- with-temp-interface 85
- with-query-interface 86

3 Using Automation 89

- Including Automation in a Lisp application 89
- Starting a remote Automation server 91
- Calling Automation methods 91
- Implementing Automation interfaces in Lisp 95
- Examples of using Automation 99

4 Automation Reference Entries 101

- com-dispatch-invoke-exception-error 101
- com-dispatch-invoke-exception-error-info 102
- call-dispatch-get-property 103
- call-dispatch-method 104
- call-dispatch-put-property 106
- com-object-dispinterface-invoke 107
- create-instance-with-events 109
- create-object 110
- define-automation-collection 111
- define-automation-component 113
- define-dispinterface-method 116
- disconnect-standard-sink 118
- do-collection-items 119
- do-connections 120
- find-component-tlb 122
- find-component-value 123
- get-active-object 124
- get-error-info 125
- get-i-dispatch-name 126
- get-i-dispatch-source-names 127
- i-dispatch 128
- interface-connect 129

- interface-disconnect 130
- lisp-variant 131
- invoke-dispatch-get-property 131
- invoke-dispatch-method 133
- invoke-dispatch-put-property 134
- make-lisp-variant 136
- :midl-type-library-file 136
- print-i-dispatch-methods 138
- query-simple-i-dispatch-interface 140
- register-active-object 141
- revoke-active-object 142
- set-error-info 142
- set-i-dispatch-event-handler 143
- set-variant 146
- simple-i-dispatch 148
- simple-i-dispatch-callback-object 150
- standard-automation-collection 151
- standard-i-connection-point-container 154
- standard-i-dispatch 155
- with-coclass 156
- with-dispatch-interface 157

5 Tools 161

- The COM Implementation Browser 161
- The COM Object Browser 165
- The COM Interface Browser 166
- Editor extensions 167

6 Self-contained examples 169

- Argument passing 169
- Aggregation 170
- OLE embedding of external components 170
- Building an ActiveX control 170
- OLE automation 171

Index 173

Preface

This manual documents the LispWorks COM/Automation API, which provides a toolkit for using Microsoft COM and Automation with Common Lisp.

For details of using OLE and ActiveX controls with the CAPI, see the class `capi:ole-control-pane` in the *CAPI User Guide and Reference Manual*.

This preface contains information you need when using the rest of the this manual. It discusses the purpose of this manual, the typographical conventions used, and gives a brief description of the rest of the contents.

Assumptions

The manual assumes that you are familiar with:

- LispWorks.
- The LispWorks FLI.
- Common Lisp and CLOS, the Common Lisp Object System.
- The functionality of Microsoft COM/Automation.

Unless otherwise stated, examples given in this document assume that the current package has `com` on its package-use-list.

Conventions used in the manual

Throughout this manual, certain typographical conventions have been adopted to aid readability.

Text which refers to Lisp forms is printed `like this`. Variables and values described in the reference sections are printed *like this*.

Entries in the reference sections are listed alphabetically and each entry is headed by the symbol name and type, followed by a number of fields providing further details. These fields consist of a subset of the following: “Summary”, “Signature”, “Method signature”, “Superclasses”, “Subclasses”, “Slots”, “Accessors”, “Readers”, “Compatibility note”, “Description”, “Notes”, “Examples”, and “See also”.

Entries with a long “Description” section usually have as their first field a short “Summary” providing a quick overview of the purpose of the symbol being described.

The “Signature” section provides details of the arguments taken by the functions and macros and values returned, separated by the => sign. The top level of parentheses is omitted, but parentheses used for destructuring in macros are included explicitly. Optional items in the syntax of macros are denoted using square brackets [*like this*]. Repeated items have an asterisk suffix like *this**.

For classes, only direct sub- and superclasses are detailed in the “Subclasses” and “Superclasses” sections of each entry.

Examples show fragments of code and sometimes the results of evaluating them

Finally, the “See also” section provides a reference to other related symbols.

Please let us know if you find any mistakes in the LispWorks documentation, or if you have any suggestions for improvements.

Example files

This manual often refers to example files in the LispWorks library via a Lisp form like this:

```
(example-edit-file "com/automation/events/ie-events")
```

These examples are files in your LispWorks installation under `lib/7-0-0-0/examples/`. You can simply evaluate the given form to view the example file.

A Description of the Contents

The manual is divided into four sections, relating to COM, Automation, graphical tools and example files respectively. The COM and Automation sections each contain a user guide and a reference chapter.

Chapter 1, *Using COM* introduces the principles behind the LispWorks COM API and describes how to use it to call COM methods and implement COM servers.

Chapter 2, *COM Reference Entries* provides a detailed description of every function, macro, variable and type in the LispWorks COM API.

Chapter 3, *Using Automation* introduces the LispWorks Automation API and describes how to use it to call Automation methods and implement Automation servers.

Chapter 4, *Automation Reference Entries* provides a detailed description of every function, macro, variable and type in the LispWorks Automation API.

Chapter 5, *Tools* describes some tools which are available in the LispWorks IDE to help with debugging applications using COM/Automation. Please note that your windows may look different from the illustrations shown. This is because some details are controlled by the theme and version of Microsoft Windows, not by LispWorks itself.

Chapter 6, *Self-contained examples* lists the example files which are relevant to the content of this manual and are available in the LispWorks library.

1

Using COM

1.1 Prerequisites

Because COM is a low level binary API, many features of the LispWorks COM API depend on the LispWorks FLI. See the *LispWorks Foreign Language Interface User Guide and Reference Manual* for details. You should also have a working knowledge of Microsoft COM.

To compile IDL files, you will need Microsoft[®] Visual C++[®] installed.

1.2 Including COM in a Lisp application

This section describes how to load COM and generate any FLI definitions needed to use it, and how to build a COM DLL.

1.2.1 Loading the modules

Before using any of the LispWorks COM API, it must be loaded by evaluating

```
(require "com")
```

1.2.2 Generating FLI definitions from COM definitions

COM definitions are typically described in one of two ways, either as IDL files, which allow the full range of COM definitions or as type libraries, which

are generally only used for Automation. Before you can use any COM functionality in a Lisp application, you need to convert the COM definitions into Lisp FLI definitions and various supporting data structures. This corresponds to using `midl.exe` or the MFC Class Wizard when writing C/C++ COM code.

To convert an IDL file, either compile it using the function `midl` or add it to a system definition with the option `:type :midl-file` and compile and load the system.

Note: types like `IDispatch` must be declared before they are used, for this conversion to work.

Conversion of type libraries is covered in Chapter 3, “Using Automation”.

1.2.3 Standard IDL files

Certain standard IDL files have already been converted to FLI definitions as part of the COM API modules. These are listed below and should not be converted again.

Table 1.1 Pre converted IDL files

IDL file	Part of Lisp module
<code>UNKNWN.IDL</code>	<code>com</code>
<code>WTYPES.IDL</code>	<code>com</code>
<code>OAIDL.IDL</code>	<code>automation</code>
<code>OLEAUTO.IDL</code>	<code>automation</code>
<code>OCIDL.IDL</code>	<code>automation</code>

1.2.4 Making a COM DLL with LispWorks

You can make a DLL with LispWorks by using `deliver` (or `save-image`) with the `:dll-exports` keyword. The value of the `:dll-exports` keyword can include the keyword `:com`, which exports (with appropriate definitions) the standard four symbols that a COM DLL needs:

```
DllGetClassObject
DllRegisterServer
DllUnregisterServer
DllCanUnloadNow
```

If no other symbols are exported, the value of `:dll-exports` can be the keyword `:com`, which means the same as the list `(:com)`. See the *LispWorks Delivery User Guide* for more details.

You can use the function `set-register-server-error-reporter` to report when calls to `DllRegisterServer` or `DllUnregisterServer` fail.

1.3 The mapping from COM names to Lisp symbols

COM names are typically a mixture of upper and lower case letters and digits, with words capitalized. These names are mapped to Lisp symbols, adding hyphens to match typical Lisp conventions for word boundaries. These examples illustrate some conversions:

Table 1.2 Examples of COM names and their corresponding Lisp names

COM name	Lisp name
IUnknown	i-unknown
pStr	p-str
DWORD	dword
IEnumVARIANT	i-enum-variant

In addition, COM methods with the `propget` attribute have a `get-` prefix added to their names and COM methods with the `propput` or `propputref` attributes have a `put-` prefix added to their names. Note that these prefixes are not used when calling methods via Automation.

To see the mapping for a particular file, look at the output while loading a converted IDL file or type library.

1.4 Obtaining the first COM interface pointer

All interaction with a remote COM server is done via its interface pointers and the most common way to obtain the first interface pointer is using the function `create-instance`. This takes the CLSID of the server and returns an interface pointer for the `i-unknown` interface unless another interface name is specified.

For example, the following will create an instance of Microsoft Word:

```
(create-instance "000209FF-0000-0000-C000-000000000046")
```

1.5 Reference counting

The lifetime of each COM interface pointer is controlled by its reference count. When a new reference to a COM interface pointer is made, the function `add-ref` should be called to increment its reference count. When a reference is removed, the function `release` should be called to decrement it again. The macro `with-temp-interface` can be useful when working with temporary interface pointers to ensure that they are released when a body of code exits in any way.

Refer to standard COM texts for more details of the reference counting rules. The LispWorks COM API does not perform any automatic reference counting (sometimes called *smart pointers* in C++).

1.6 Querying for other COM interface pointers

An interface pointer can be queried to discover if the underlying object supports other interfaces. This is done using the function `query-interface`, passing the interface pointer and the `refiid` of the interface to query. A `refiid` is either a foreign pointer to a GUID structure or a `symbol` naming a COM interface as described in Section 1.3.

For example, the function below will find the COM interface pointer for its `i-dispatch` interface:

```
(defun find-dispatch-pointer (ptr)
  (query-interface ptr 'i-dispatch))
```

The macro `with-query-interface` can be used to query an interface pointer and automatically release it again on exit from a body of code.

1.7 Calling COM interface methods

The macros `call-com-interface` and `with-com-interface` are used to call COM methods. To call a COM method, you need to specify the interface name, the method name, a COM interface pointer and suitable arguments. The interface and method names are given as symbols named as in Section 1.3 and the COM interface pointer is a foreign pointer of type `com-interface`. In both macros, the *args* and *values* are as specified in the Section 1.7.1.

The `with-com-interface` macro is useful when several methods are being called with the same COM interface pointer, because it establishes a local macro that takes just the method name and arguments.

For example, the following are equivalent ways of calling the `move` and `resize` methods of a COM interface pointer `window-ptr` for the `i-window` interface:

```
(progn
  (call-com-interface (window-ptr i-window move) 10 10)
  (call-com-interface (window-ptr i-window resize) 100 100))

(with-com-interface (call-window-ptr i-window) window-ptr
  (call-window-ptr move 10 10)
  (call-window-ptr resize 100 100))
```

1.7.1 Data conversion when calling COM methods

All IDL definitions map onto FLI definitions, mirroring the mapping that `midl.exe` does for C/C++. However, IDL provides some additional type information that C/C++ lacks (for instance the `string` attribute), so there are some additional conversions that Lisp performs when it can.

The COM API uses the information from the IDL to convert data between FLI types and Lisp types where appropriate for arguments and return values of COM method calls. In particular:

- Primitive integer types are represented as Lisp integers.
- Primitive char types are represented as Lisp characters.
- Primitive float types are represented as Lisp float types.
- COM interface pointers are FLI objects represented as objects of type `com-interface`, which supports type checking of the interface name.
- Except as detailed below, all other COM types are represented as their equivalent FLI types. This includes other pointer types and structs.

In COM, all parameters have a *direction* which can be either *in*, *out* or both *in* and *out* (referred to as *in-out* here). Arguments and values for client-side COM method calls reflect the direction as described in the following sections. For a complete version of the example code, see the file:

```
(example-edit-file "com/manual/args/args-calling")
```

1.7.1.1 In parameters

In parameters are passed as positional arguments in the order they are specified and do not affect the return values.

- A parameter with the `string` attribute can be passed either as a foreign pointer or as a Lisp string (converted to a foreign string with dynamic extent for the duration of the call).
- A parameter whose type is either an array type or a pointer type with a `size_is` attribute can be passed either as a foreign pointer or, if the element type is not a foreign aggregate type, as a Lisp array of the appropriate rank (converted to a foreign array with dynamic extent for the duration of the call).
- Otherwise, the Lisp value is converted using the FLI according to the mapping of types defined above.

For example, given the IDL

```
import "unknwn.idl";

[ object,
  uuid(E37A70A0-EFC9-11D5-BF02-000347024BE1)
]
interface IArgumentExamples : IUnknown
{
  typedef [string] char *argString;

  HRESULT inMethod([in] int inInt,
                  [in] argString inString,
                  [in] int inArraySize,
                  [in, size_is(inArraySize)] int *inArray);
}
```

the method `in-method` can be called with Lisp objects like this:

```
(let ((array #(7 6)))
  (call-com-interface (arg-example i-argument-examples
                              in-method)
                    42
                    "the answer"
                    (length array)
                    array))
```

or with foreign pointers like this:

```

(fli:with-dynamic-foreign-objects ()
  (let* ((farray-size 2)
        (farray (fli:allocate-dynamic-foreign-object
                  :type :int
                  :nelems farray-size
                  :initial-contents '(7 6))))
    (fli:with-foreign-string (fstring elt-count byte-count)
      "the answer"
      (declare (ignore elt-count byte-count))
      (call-com-interface (arg-example i-argument-examples
                                     in-method)
                          42
                          fstring
                          farray-size
                          farray))))

```

Note that the `int` arguments are always passed as Lisp `integer` because `int` is a primitive type.

1.7.1.2 Out parameters

Out parameters are always of type pointer in COM and never appear as positional arguments in the Lisp call. Instead, there is a keyword argument named after the parameter, which can be used to pass an object to be modified by the method. In addition, each *out* parameter generates a return value, which will be `eq` to the value of keyword argument if it was passed and otherwise depends on the type of the parameter as described below.

- If the value of the keyword argument is a foreign pointer then it is passed directly to the method and is expected to point to an object of the appropriate size to contain the returned data.
- If the value of the keyword argument is `nil` then a null pointer is passed to the method.
- Except where specified below, if the keyword argument is omitted, a foreign object with dynamic extent is created to contain the value and a pointer to this object is passed to the method. On return, the contents maybe be converted back to a Lisp object as specified.
- A parameter with the `string` attribute is converted to a Lisp string if the keyword is not passed. If the keyword is passed, the memory for the

string might need to be freed by `co-task-mem-free` if nothing else does this.

- A parameter whose type is either an array type or a pointer type with a `size_is` attribute will be converted to a Lisp array if the keyword is not passed and the element type is not a foreign aggregate type. If the keyword argument is not passed then a new Lisp array is made. If the value of the keyword argument is a Lisp array then that is filled.
- For a parameter whose type is a foreign aggregate type, such as `struct`, the keyword argument must be passed and its value must be as a foreign pointer. This pointer is passed directly to the method.
- For a parameter with the `iid_is` attribute, a `com-interface` pointer is returned using the indicated iid parameter to control the interface name.
- Otherwise, the dynamic extent foreign pointer is dereferenced to obtain the Lisp return value, as if by calling `fl:dereference`.

For example, given the IDL

```
import "unknwn.idl";

[ object,
  uuid(E37A70A0-EFC9-11D5-BF02-000347024BE1)
]
interface IArgumentExamples : IUnknown
{
  typedef [string] char *argString;

  HRESULT outMethod([out] int *outInt,
                    [out] argString *outString,
                    [in] int outArraySize,
                    [out, size_is(outArraySize)] int *outArray);
}
```

the method `out-method` can return Lisp objects like this:

```
(multiple-value-bind (hres int string array)
  (call-com-interface (arg-example i-argument-examples
                               out-method)
                    8)
  ;; int is of type integer
  ;; string is of type string
  ;; array is of type array
)
```

or fill an existing array like this:

```
(let ((out-array (make-array 5)))
  (multiple-value-bind (hres int string array)
    (call-com-interface (arg-example i-argument-examples
                                   out-method)
                      (length out-array)
                      :out-array out-array)
    ;; int is of type integer
    ;; string is of type string
    ;; array is eq to out-array and was filled
  ))
```

or set the contents of foreign memory like this:

```
(fli:with-dynamic-foreign-objects ((out-int :int)
                                   (out-string WIN32:LPSTR))
  (let* ((out-farray-size 5)
         (out-farray (fli:allocate-dynamic-foreign-object
                       :type :int
                       :nelems out-farray-size)))
    (multiple-value-bind (hres int string array)
      (call-com-interface (arg-example i-argument-examples
                                       out-method)
                        out-farray-size
                        :out-int out-int
                        :out-string out-string
                        :out-array out-farray)
      ;; Each foreign pointer contains the method's results
      ;; int is the foreign pointer out-int
      ;; string is the foreign pointer out-string
      ;; array is the foreign pointer out-array
      ;; Note that the string must be freed as follows:
      (co-task-mem-free (fli:dereference out-string))))))
```

1.7.1.3 In-out parameters

In-out parameters are always of type pointer in COM and are handled as a mixture of *in* and *out*. In particular, they have both a positional parameter and a keyword parameter, which can be used to control the value passed and conversion of the value returned respectively. Each *in-out* parameter generates a return value, which will be `eq` to the value of the keyword argument if it was passed and otherwise depends on the type of the parameter as below.

- As for *out* parameters, if the value of the keyword argument is a foreign pointer then it is passed directly to the method and is expected to be of the appropriate size to contain the returned data. If the value of the keyword argument is `nil` then a null pointer is passed to the COM call. The positional argument should be `nil` in these cases. If the keyword argument not passed, a foreign object with dynamic extent is created to contain the value, initialized with data from the positional argument before calling the method and possibly converted back to a Lisp value on return.
- For a parameter with the `string` attribute, the positional argument is handled as for the *in* argument `string` case and the keyword argument is handled as for the *out* argument `string` case. The functions `co-task-mem-alloc` and `co-task-mem-free` should be used to manage the memory for the string itself.
- For a parameter whose type is a non-aggregate array type or a pointer to a non-aggregate type that has the `size_is` attribute, the positional argument is handled as for the *in* argument array case and the keyword argument is handled as for the *out* argument array case. To update an existing array, pass it as both the positional and keyword argument values.
- For a parameter whose type is a foreign aggregate type, the keyword argument must be passed and its value must be a foreign pointer. This pointer is passed directly to the method and the positional argument should be `nil`.
- Otherwise, a foreign object with dynamic extent is created, set to contain the value of positional argument before calling the method and

dereferenced on return to obtain the Lisp return value, as if by calling `fli:dereference`.

For example, given the IDL

```
import "unknwn.idl";

[ object,
  uuid(E37A70A0-EFC9-11D5-BF02-000347024BE1)
]
interface IArgumentExamples : IUnknown
{
  typedef [string] char *argString;

  HRESULT inoutMethod([in, out] int *inoutInt,
                      [in, out] argString *inoutString,
                      [in] int inoutArraySize,
                      [in, out, size_is(inoutArraySize)]
                      int *inoutArray);
}
```

the method `inout-method` can receive and return Lisp objects like this:

```
(let ((in-array #(7 6)))
  (multiple-value-bind (hres int string array)
    (call-com-interface (arg-example i-argument-examples
                                  inout-method)
                       42
                       "the answer"
                       (length in-array)
                       in-array)
    ;; int is of type integer
    ;; string is of type string
    ;; array is of type array
  ))
```

or fill an existing array like this:

```
(let* ((in-array #(7 6))
      (out-array (make-array (length in-array))))
  (multiple-value-bind (hres int string array)
    (call-com-interface (arg-example i-argument-examples
                                   inout-method)
                       42
                       "the answer"
                       (length in-array)
                       in-array
                       :inout-array out-array)
    ;; int is of type integer
    ;; string is of type string
    ;; array is eq to out-array, which was filled
  ))
```

or update an existing array like this:

```
(let* ((inout-array #(7 6))
      (multiple-value-bind (hres int string array)
        (call-com-interface (arg-example i-argument-examples
                                       inout-method)
                           42
                           "the answer"
                           (length inout-array)
                           inout-array
                           :inout-array inout-array)
        ;; int is of type integer
        ;; string is of type string
        ;; array is eq to inout-array, which was updated
      ))
```

1.7.2 Error handling

Most COM methods return an integer `hresult` to indicate success or failure, which can be checked using `succeeded`, `s_ok`, `hresult-equal` or `check-hresult`.

In addition, after calling a COM method that provides extended error information, you can call the function `get-error-info` to obtain more details of any error that occurred. This is supplied with a list of *fields*, which should be keywords specifying the parts of the error information to obtain.

For example, in the session below, `tt` is a COM interface pointer for the `i-test-suite-1` interface:

```

CL-USER 186 > (call-com-interface (tt i-test-suite-1 fx))

"in fx"           ;; implementation running
-2147352567       ;; the error code DISP_E_EXCEPTION

CL-USER 187 > (get-error-info :fields '(:description
                                         :source))
("foo" "fx")

CL-USER 188 >

```

1.8 Implementing COM interfaces in Lisp

Lisp implementations of COM interfaces are created by defining an appropriate class and then defining COM methods for all the interfaces implemented by this class.

The class can inherit from `standard-i-unknown` to obtain an implementation of the `i-unknown` interface. This superclass provides reference counting and an implementation of the `query-interface` method that generates COM interface pointers for the interfaces specified in the class definition. It also supports *aggregation*.

There are two important things to note about COM classes and methods:

- The implementation objects and COM interface pointers are different things: an interface pointer must be queried from the implementation object explicitly and the function `com-object-from-pointer` can be used to obtain an object from an interface pointer. This is shown in Figure 1.1 below.
- COM methods are not defined with `defmethod` because they have very specific conventions for passing arguments and returning values that are different from those of Lisp.




Figure 1.1 The relationship between an Lisp object and its COM interface pointers

1.8.1 Steps required to implement COM interfaces

To implement a COM interface in Lisp, you need the following:

1. Some COM interface definitions, converted to Lisp as specified in Section 1.2.2
2. A COM object class defined with the macro `define-com-implementation`, specifying the interface(s) to implement.
3. Implementations of the methods using `define-com-method`.
4. If the objects are to be created by another process, a description of the class factories created with `make-factory-entry` and registered with `register-class-factory-entry`.
5. Initialization code to call `co-initialize`. It should also call `start-factories` in a thread that will be processing Windows messages (for instance a CAPI thread) if you have registered class factories.

1.8.2 The lifecycle of a COM object

Since COM objects can be accessed from outside the Lisp world, possibly from a different application, their lifetimes are controlled more carefully than those

of normal Lisp objects. The diagram below shows the lifecycle of a typical COM object.




Figure 1.2 The lifecycle of a COM object

Each COM object goes through the following stages.

1. CLOS object initialization.

In the first stage, the object is created by a call to `make-instance`, either by a class factory (see Section 1.8.3) or explicitly by the application. The normal CLOS initialization mechanisms such as `initialize-instance` can be used to initialize the object. During this stage, the object is known only to Lisp and can be garbage collected if the next stage is not reached.

2. COM initialization.

At some point, the server makes the first COM interface pointer for the object by invoking the COM method `query-interface`, either automatically in the class factory or explicitly using by using macros such as `query-object-interface` or `call-com-object`. When this happens, the object's reference count will become 1 and the object will be stored in

the COM runtime system. In addition, the generic function `com-object-initialize` is called to allow class-specific COM initialization to be done.

3. COM usage.

In this stage, the object is used via its COM interface pointers by a client or directly by Lisp code in the server. Several COM interface pointers might be created and each one contributes to the overall reference count of the object.

4. COM destruction.

This stage is entered when the reference count is decremented to zero, which is triggered by all the COM interface pointers being released by their clients. The generic function `com-object-destructor` is called to allow class-specific COM cleanups and the object is removed from the COM runtime system. From now on, the object is not known to COM world.

5. Garbage collection.

The final stage of an object's lifecycle is the normal Lisp garbage collection process, which removes the object from memory when there are no more references to it.

1.8.3 Class factories

The LispWorks COM runtime provides an implementation of the *class factory* protocol, which will construct COM objects on demand. The class factory implementation supports *aggregation* when passed an outer unknown pointer.

Class factories are described by objects created with `make-factory-entry` and must be registered with the COM runtime using `register-class-factory-entry`. The function `start-factories` should be called when the application initializes to start all the registered class factories.

When using the Automation API described in Chapter 3 and Chapter 4, class factories are created and registered automatically by the `define-automation-component` macro if appropriate.

1.8.4 Unimplemented methods

If the class does not define all the COM methods for the interfaces it implements, then some of those methods may be inherited from superclasses (see Section 1.8.5). If there is no direct or inherited definition of a method, then a default method that returns `E_NOTIMPL` will be provided automatically. The default method also fills all *out* arguments with null bytes and ignores all *in* and *in-out* arguments except those needed to compute the size of arrays for filling *out* arguments.

1.8.5 Inheritance

A COM object class will inherit COM method implementations from its superclasses if no direct method is defined. However, unlike Lisp methods where an effective method is computed from the set of applicable methods for each generic function, COM methods are always inherited in groups via their defining interface. This is because the interface is used to call a COM method, not the COM object

Specifically, each method is inherited from the first class in the class precedence list that implements the interface where the method is declared. No attempt is made to search further down the class precedence list if this class is using the unimplemented method definition described in Section 1.8.4.

1.8.5.1 An example of multiple inheritance

The inheritance rules may lead to unexpected results in the case of multiple inheritance. For example, consider the following IDL:

```
// IDL definition of IFoo
import "unknwn.idl";

[ uuid(7D9EB760-E4E5-11D5-BF02-000347024BE1) ]
interface IFoo : IUnknown
{
    HRESULT meth1();
    HRESULT meth2();
    HRESULT meth3();
}
```

and these three (partial) implementations of the interface `i-foo`.

1. An implementation with no definition of `meth2`:

```
(define-com-implementation foo-impl-1 ()
  ()
  (:interfaces i-foo))

(define-com-method meth1 ((this foo-impl-1))
  s_ok)

(define-com-method meth3 ((this foo-impl-1))
  s_ok)
```

2. An implementation with no definition except `meth2`:

```
(define-com-implementation foo-impl-2 ()
  ()
  (:interfaces i-foo))

(define-com-method meth2 ((this foo-impl-2))
  s_ok)
```

3. A combined implementation, inheriting from steps 1 and 2.

```
(define-com-implementation foo-impl-12 (foo-impl-1
                                         foo-impl-2)
  ()
  (:interfaces i-foo))
```

In step 3, the class `foo-impl-12` implements the interface `i-foo`, but inherits all the `i-foo` method definitions from `foo-impl-1`, which is the first class in the class precedence list that implements that interface. These method definitions include the "unimplemented" definition of `meth2` in `foo-impl-1`, which hides the definition in the other superclass `foo-impl-2`. As a result, when the following form is evaluated with `p-foo` created from an instance of `foo-impl-12`:

```
(let ((object (make-instance 'foo-impl-12)))
  (with-temp-interface (p-foo)
    (nth-value 1 (query-object-interface
                  foo-impl-12
                  object
                  'i-foo))
    (with-com-interface (call-p-foo i-foo) p-foo
      (values (call-p-foo meth1)
              (call-p-foo meth2)
              (call-p-foo meth3))))))
```

the three values are `S_OK`, `E_NOTIMPL` and `S_OK`.

1.8.5.2 A second example of multiple inheritance

Here is a further extension to the example in Section 1.8.5.1, with an additional interface `i-foo-ex` that inherits from `i-foo` as in the following IDL:

```
[ uuid(7D9EB761-E4E5-11D5-BF02-000347024BE1) ]
interface IFooEx : IFoo
{
    HRESULT meth4();
}
```

This interface has the following additional implementations:

1. An implementation defining all the methods in `i-foo-ex`:

```
(define-com-implementation foo-ex-impl-1 ()
  (:interfaces i-foo-ex))

(define-com-method meth1 ((this foo-ex-impl-1)
  s_ok)

(define-com-method meth2 ((this foo-ex-impl-1)
  s_ok)

(define-com-method meth3 ((this foo-ex-impl-1)
  s_ok)

(define-com-method meth4 ((this foo-ex-impl-1)
  s_ok)
```

2. A combined implementation, inheriting from step 3 from Section 1.8.5.1 and step 1 above.

```
(define-com-implementation foo-ex-impl-2 (foo-impl-12
                                          foo-ex-impl-1)
  ()
  (:interfaces i-foo-ex))
```

In step 2, the class `foo-ex-impl-2` implements the interface `i-foo-ex` and is a subclass of `foo-ex-impl-1`, which implements `i-foo`. When the following form is evaluated with `p-foo-ex` created from an instance of `foo-ex-impl-2`:

```
(let ((object (make-instance 'foo-ex-impl-2)))
  (with-temp-interface (p-foo-ex)
    (nth-value 1 (query-object-interface
                  foo-ex-impl-2
                  object
                  'i-foo-ex))
    (with-com-interface (call-p-foo i-foo-ex) p-foo-ex
      (values (call-p-foo meth1)
              (call-p-foo meth2)
              (call-p-foo meth3)
              (call-p-foo meth4))))))
```

the four values are `S_OK`, `E_NOTIMPL`, `S_OK` and `S_OK`.

Note that, even though `foo-ex-impl-2` only explicitly implements `i-foo-ex`, the methods `meth1`, `meth2` and `meth3` were declared in its parent interface `i-foo`. This means that their definitions (including the "unimplemented" definition of `meth2`) are inherited from `foo-impl1` (via `foo-impl-12`), because `foo-impl-12` is before `foo-ex-impl-2` in the class precedence list of `foo-ex-impl-2`. Only `meth4`, which is declared in `i-foo-ex`, is inherited from `foo-ex-impl-1`.

1.8.6 Data conversion in define-com-method

All IDL definitions map onto FLI definitions, mirroring the mapping that `midl.exe` does for C/C++. However, IDL provides some additional type information that C/C++ lacks (for instance the `string` attribute), so there are some additional conversions that Lisp performs when it can. For a complete example of data conversion, see the file:

```
(example-edit-file "com/manual/args/args-impl")
```

1.8.6.1 FLI types

The COM API uses the information from the IDL to convert data between FLI types and Lisp types where appropriate for arguments and return values of COM method definitions. In particular:

- Primitive integer types are represented as Lisp integers
- Primitive char types are represented as Lisp characters.
- Primitive float types are represented as Lisp float types.

- COM interface pointers are represented as objects of type `com-interface`, which supports type checking of the interface name.
- All other types are represented as their equivalent FLI types. This includes other pointer types and structs.

Each argument in the IDL has a corresponding argument in the `define-com-method` form. In addition, each argument has a *pass-style* which specifies whether additional conversions are performed.

If the *pass-style* of a parameter is `:foreign`, then the value will be exactly what the FLI would provide, i.e. foreign pointers for strings and for all *out* or *in-out* parameters (which are always pointers in the IDL).

If the *pass-style* of a parameter is `:lisp`, then the conversions described in the following sections will be done.

1.8.6.2 In parameters

For *in* parameters:

- A parameter with the `string` attribute will be converted to a Lisp string. The string should not be destructively modified by the body.
- A parameter of COM type `BSTR` will be converted to a Lisp string. The string should not be destructively modified by the body.
- A parameter of COM type `VARIANT*` will be converted to a Lisp object according to the VT code in the variant (see Table 3.1, page 93).
- A parameter of COM type `SAFEARRAY (type)` or `SAFEARRAY (type) *` will be converted to a Lisp array. The elements of type *type* are converted as in Table 3.1.
- A parameter of COM type `VARIANT_BOOL` will be converted to `nil` (for zero) or `t` (for any other value). Note that a parameter of type `BOOL` will be converted to an `integer` because type libraries provide no way to distinguish this case from the primitive integer type.
- A parameter whose type is an array type or a pointer type with a `size_is` attribute will be converted to a temporary Lisp array. The Lisp array might have dynamic extent.

- Otherwise, the value is converted to a Lisp value using the FLI according to the mapping of types defined in Section 1.8.6.1.

1.8.6.3 Out parameters

For *out* parameters:

- A parameter whose type is an array type or a pointer type with a `size_is` attribute will be converted to a Lisp array of the appropriate size allocated for the dynamic extent of the body forms. After the body has been evaluated, the contents of the array will be copied into the foreign array that the caller has supplied.
- For other types, the parameter will be `nil` initially and the body should use `setq` to set it to the value to be returned.

In the latter case, the value will be converted to a foreign object after the body has been evaluated. The following conversions are done:

- For a parameter with the `string` attribute, a Lisp string will be converted to a foreign string using `CoTaskMemAlloc()`.
- For a parameter of COM type `BSTR*`, a Lisp string will be converted to a foreign string using `SysAllocString()`.
- For a parameter of COM type `VARIANT*`, the value can be any Lisp value, with the VT code being set according to the Lisp type (see Table 3.1, page 93). If exact control is required, use the *pass-style* `:foreign` and the function `set-variant`.
- For a parameter of COM type `SAFEARRAY (type) *`, the value can be either a foreign pointer to an appropriate `SAFEARRAY` or a Lisp array. In the latter case, a new `SAFEARRAY` is created which contains the elements of the Lisp array converted as in Table 3.1.
- For a parameter of COM type `VARIANT_BOOL*`, the value can be a generalized boolean.
- Otherwise, the Lisp value will be converted using the FLI according to the mapping of types defined in Section 1.8.6.1.

1.8.6.4 In-out parameters

For *in-out* parameters:

- A parameter whose type is an array type or a pointer type with a `size_is` attribute will be converted to a Lisp array of the appropriate size allocated for the dynamic extent of the body forms. The initial contents of the Lisp array will be taken from the foreign array which was passed by the caller. After the body has been evaluated, the contents of the Lisp array will be copied back into the foreign array.
- For a parameter with the `string` attribute, the parameter will be converted to a Lisp string. To return a different string, the parameter should be set to another (non `eq`) Lisp string, which will cause the original foreign string to be freed with `CoTaskMemFree()` and a new foreign string allocated with `CoTaskMemAlloc()`. The initial string should not be destructively modified by the body.
- For a parameter of COM type `BSTR*`, the parameter will be converted to a Lisp string. To return a different string, the parameter should be set to another (non `eq`) Lisp string, which will cause the original foreign string to be freed with `SysFreeString()` and a new foreign string allocated with `SysAllocString()`.
- For parameters of COM type `VARIANT*`, the parameter will be converted to a Lisp object (see Table 3.1, page 93). To return a different value, the parameter should be set to another (non `eq`) value, which will be placed back into the `VARIANT` with the VT code being set according to the Lisp type (see Table 3.1, page 93). If exact control of the VT code is required, use the *pass-style* `:foreign` and the function `set-variant`.
- For parameters of COM type `SAFEARRAY (type) *`, the parameter will be converted to a Lisp array. The elements of type `type` are converted as in Table 3.1. To return a different value, the parameter should be set to another (non `eq`) value, which can be either a foreign pointer to an appropriate `SAFEARRAY` or a Lisp array. In the latter case, a new `SAFEARRAY` is created which contains the elements of the Lisp array converted as in Table 3.1.
- For parameter of COM type `VARIANT_BOOL*`, the parameter will be `nil` or `t` according to the initial value (zero or non zero). To return a differ-

ent value, set the parameter to a new value, which can be a generalized boolean.

1.9 Calling COM object methods from Lisp

Within the implementation of a COM object, the macros `call-com-object` and `with-com-object` can be used to call COM methods directly for a COM object without using an interface pointer. To call a COM method, you need to specify the class name, the method name, the interface name if the method name is not unique, a COM object and suitable arguments. The class name is a symbol as used in the `define-com-implementation` form and can be a superclass of the actual object class. The method and interface names are given as symbols named as in Section 1.3. and the arguments and values are as specified below in Section 1.9.1. These macros should be used with caution because they assume that the caller knows the implementation's *pass-style* for all the arguments.

The `with-com-object` macro is useful when several methods are being called with the same COM object, because it establishes a local macro that takes just the method name and arguments.

1.9.1 Data conversion when calling COM object methods

No explicit argument or return value conversion is done by `call-com-object` or `with-com-object`. As a result, every argument must be passed as a positional argument and must be of the type expected by the method's implementation. The allowable types are described in the following sections.

1.9.1.1 In parameters

For *in* parameters,

- For a parameter with the `string` attribute, the value can be a Lisp string.
- For a parameter of COM type `BSTR`, the value can be a Lisp string.
- For a parameter whose type is an array type or a pointer type with a `size_is` attribute, the value can be a Lisp array of the appropriate rank and dimension.

- Otherwise, the value should match what the FLI would generate for the parameter's type.

1.9.1.2 Out parameters

For *out* parameters,

- If `nil` is passed, the value from the method is returned without any conversion.
- For a parameter whose type is an array type or a pointer type with a `size_is` attribute, the value can be a Lisp array. The contents of the array will be modified by the method and the array will be returned as a value.
- Otherwise, the value should be a foreign pointer of the type that the FLI would generate for the parameter's type. The foreign pointer will be returned as a value.

1.9.1.3 In-out parameters

For *in-out* parameters,

- For a parameter whose type is an array type or a pointer type with a `size_is` attribute, the value can be a Lisp array. The contents of the array will be modified by the method and the array will be returned as a value.
- For a parameter with the `string` attribute, the parameter can be a Lisp string. The value of the parameter at the end of the body will be returned as a value.
- For a parameter of COM type `BSTR*`, the parameter can be a Lisp string. The value of the parameter at the end of the body will be returned as a value.
- For parameters of COM type `VARIANT*`, the parameter can be any Lisp object. The value of the parameter at the end of the body will be returned as a value.
- If the value is a foreign pointer of the type that the FLI would generate for the parameter's type then the foreign object it points to will be the

value of the parameter. The foreign pointer will be returned as a value, with the new contents as modified (or not) by the method.

- Otherwise, the parameter is passed directly to the method and the value of the parameter at the end of the body will be returned as a value.

2

COM Reference Entries

This chapter documents COM functionality.

add-ref

Function

Summary	Increments the reference count of a COM interface pointer.	
Package	<code>com</code>	
Signature	<code>add-ref <i>interface-ptr</i> => <i>ref-count</i></code>	
Arguments	<code><i>interface-ptr</i></code>	A COM interface pointer.
Values	<code><i>ref-count</i></code>	The new reference count.
Description	Each COM interface pointer has a reference count which is used by the server to control its lifetime. The function <code>add-ref</code> should be called whenever an extra reference to the interface pointer is being made. The function invokes the COM method <code>IUnknown::AddRef</code> so the form <code>(add-ref ptr)</code> is equivalent to using <code>call-com-interface</code> as follows:	

```
(call-com-interface (ptr i-unknown add-ref))
```

Example `(add-ref p-foo)`

See also `release`
`interface-ref`
`query-interface`
`call-com-interface`

automation-server-command-line-action

Function

Summary Reports what action was specified for the automation server.

Package `com`

Signature `automation-server-command-line-action => action`

Arguments None.

Values One of the keywords `:register`, `:unregister` or `:embedding`, or `nil`.

Description The function `automation-server-command-line-action` inspects the command line to see what action was specified for the automation server. The possible return values have the following meanings:

<code>:register</code>	The server should register itself (by <code>register-server</code>). Specified by <code>/RegServer</code> .
<code>:unregister</code>	The server should unregister itself (by <code>unregister-server</code>). Specified by <code>/UnRegServer</code> .
<code>:embedding</code>	The server was run with <code>/Embedding</code> or <code>-Embedding</code> .
<code>nil</code>	No recognized action.

See also `register-server`
`unregister-server`

automation-server-main

Function

Summary For use as the main function for an automation server.

Package `com`

Signature `automation-server-main &key exit-delay exit-function new-process force-server forced-exit-delay quit-on-registry-error handle-registry-error`

Arguments *exit-delay* A non-negative real number.

exit-function A function specifier.

new-process A boolean.

force-server A boolean.

forced-exit-delay A non-negative real number.

quit-on-registry-error
A boolean.

handle-registry-error
A boolean.

Description The function `automation-server-main` is for use as the main function for an automation server.

exit-delay, if supplied, sets the exit delay for `automation-server-top-loop`, by calling `set-automation-server-exit-delay` with it.

exit-function is an *exit-function* for `automation-server-top-loop`. The default value of *exit-function* is `server-can-exit-p`.

new-process controls whether to run `automation-server-top-loop` in its own process.

force-server controls whether to force running the automation server even if the application starts normally. The default value of *force-server* is `t`.

forced-exit-delay specifies the *exit-delay* in seconds when the server is forced.

`automation-server-main` checks the command line (using `automation-server-command-line-action`) for what action it should do, and then does it.

If the action is `:register` or `:unregister`, `automation-server-main` tries register or unregister the server (using `register-server` and `unregister-server`). If the operation succeeds, `automation-server-main` just returns `:register` or `:unregister`.

handle-registry-error controls what happens if there is an error while trying to register or unregister. If `nil` is supplied then `error` is called, and if a non-`nil` value is supplied, then the error is handled. If *handle-registry-error* is not supplied, by default the error is handled, but if the command line contains `-debug` or `/debug`, the error is not handled. The default value of *handle-registry-error* is `nil`.

quit-on-registry-error controls what happens if an error occurs during registration. If it is non-`nil` (the default), then `automation-server-main` calls `quit` with the appropriate *status* value (5). Otherwise it returns `:register-failed` or `:unregister-failed`. The default value of *quit-on-registry-error* is `t`.

If the command line action is `:embedding` or the action is `nil` and *force-server* is non-`nil` (the default) then `automation-server-main` runs the server by using `automation-server-top-loop`. If *new-process* is `nil` (the default), `automation-server-top-loop` is called on the current process. In this case `automation-server-main` returns only after automa-

`automation-server-top-loop` exits (and the server was closed). If `new-process` is true, `automation-server-top-loop` is called on its own process and `automation-server-main` returns immediately.

If the server is "forced", that is the action is `nil` but `force-server` is non-`nil`, and `forced-exit-delay` is non-`nil`, the `exit-delay` is set to `forced-exit-delay` (using `set-automation-server-exit-delay`). This overrides the value of the argument `exit-delay`.

`automation-server-main` returns the result of `automation-server-command-line-action`, except in the case of registry failure as described above.

Notes

1. `automation-server-main` is intended to be used as the main function in an automation server that is delivered as an executable (rather than as a DLL).
2. When the application acts only as automation server, `automation-server-main` can be the function argument to `deliver`, or the `restart-function` in `save-image` (`multi-processing t` is needed too). It will deal correctly with registration when the command line argument is supplied, otherwise runs the server until it can exit and then returns (the application will exit because there will not be any other processes).
3. When the application also needs to do other things, `automation-server-main` can be used to run the server. Note that with the default values when `automation-server-main` runs the server it does not return until the server exits, so you need to either pass `:new-process t`, or run it on its own process. You will also need to consider whether to wait when failing to register, and hence may want to pass `:quit-on-registry-failure nil`.

See also

`automation-server-top-loop`
`automation-server-command-line-action`
`set-automation-server-exit-delay`

automation-server-top-loop*Function*

Summary	A function to run a COM server.	
Package	com	
Signature	<code>automation-server-top-loop &key <i>exit-delay</i> <i>exit-function</i></code>	
Arguments	<i>exit-function</i>	A function designator.
	<i>exit-delay</i>	A non-negative real number specifying a time in seconds.
Description	<p>The function <code>automation-server-top-loop</code> calls <code>co-initialize</code> and <code>start-factories</code>, and then processes messages, until the server can exit. Since COM works by messages, it will end up processing all COM requests.</p> <p><i>exit-function</i> determines when the server can exit. It defaults to <code>server-can-exit-p</code>, which is normally the right function. This returns <code>t</code> when the COM server is not used and there are no other "working processes". See the documentation for <code>server-can-exit-p</code>. When <i>exit-function</i> is supplied, it needs to be a function of no arguments which returns true when the server can exit. The <i>exit-function</i> is used like a wait function: it is called repeatedly, it needs to be reasonably fast, and should not wait for anything.</p> <p>Once the server can exit, <code>automation-server-top-loop</code> delays exiting for another period of time, <i>exit-delay</i> seconds. <i>exit-delay</i> defaults to 5, and can be set by calling <code>set-automation-server-exit-delay</code>. If supplied, <i>exit-delay</i> is passed to <code>set-automation-server-exit-delay</code> on entry. However, later calls to <code>set-automation-server-exit-delay</code> can change the <i>exit-delay</i>.</p> <p>After the delay <code>automation-server-top-loop</code> checks again by calling <i>exit-function</i>. If this returns false it goes on to process messages. Otherwise it stops the factories, calls <code>co-uninitialize</code> and returns.</p>	

Notes

1. `automation-server-top-loop` interacts with the `deliver` keyword `:quit-when-no-windows`, such that the delivered application does not `quit` even after all CAPI windows are closed as long as `automation-server-top-loop` has not returned.
2. `automation-server-top-loop` does not return while the server is active. Typically it will be running on its own process.
3. `automation-server-top-loop` uses `mp:general-handle-event` to process Lisp events, so it is possible to run in the same thread operations that rely on such messages. In particular, CAPI windows can start on the same process. However, all COM input is processed in this thread, so it is probably better to start CAPI windows on other processes, so that they do not interfere with each other.
4. `automation-server-top-loop` does not return a useful value.

See also

`start-factories`
`stop-factories`
`automation-server-main`
`server-can-exit-p`
`set-automation-server-exit-delay`

call-com-interface

Macro

Summary Invokes a method from a particular COM interface.

Package `com`

Signature `call-com-interface spec arg* => values`
`spec ::= (interface-ptr interface-name method-name)`

Arguments	<i>spec</i>	The interface pointer and a specification of the method to be called.
	<i>interface-ptr</i>	A form which is evaluated to yield a COM interface pointer.
	<i>interface-name</i>	A symbol which names the com interface. It is not evaluated.
	<i>method-name</i>	A symbol which names the method. It is not evaluated.
	<i>arg</i>	Arguments to the method (see Section 1.7.1, “Data conversion when calling COM methods” for details).
Values	<i>values</i>	Values from the method (see Section 1.7.1, “Data conversion when calling COM methods” for details).
Description	The macro <code>call-com-interface</code> invokes the method <i>method-name</i> for the COM interface <i>interface-name</i> , which should be the type or a supertype of the actual type of <i>interface-ptr</i> . The <i>args</i> and <i>values</i> are described in detail in Section 1.7.1, “Data conversion when calling COM methods”.	
Example	This example invokes the COM method <code>GetTypeInfo</code> in the interface <code>IDispatch</code> .	
	<pre>(defun get-type-info (disp tinfo &key (locale LOCALE_SYSTEM_DEFAULT)) (multiple-value-bind (hres typeinfo) (call-com-interface (disp i-dispatch get-type-info) tinfo locale) (check-hresult hres 'get-type-info) typeinfo))</pre>	
See also	<code>with-com-interface</code> <code>query-interface</code>	

add-ref
release

call-com-object

Macro

Summary	Invokes a COM method on a COM object.	
Package	com	
Signature	<code>call-com-object <i>spec</i> <i>arg</i>* => <i>values</i></code> <code><i>spec</i> ::= (object <i>class-name</i> <i>method-spec</i> &key <i>interface</i>)</code> <code><i>method-spec</i> ::= <i>method-name</i> (<i>interface-name</i> <i>method-name</i>)</code>	
Arguments	<i>spec</i>	The object and a specification of the method to be called.
	<i>object</i>	A form which is evaluated to yield a COM object.
	<i>class-name</i>	A symbol which names the COM implementation class. It is not evaluated.
	<i>method-spec</i>	Specifies the method to be called. It is not evaluated.
	<i>method-name</i>	A symbol naming the method to call.
	<i>interface-name</i>	A symbol naming the interface of the method to call. This is only required if the implementation class <i>class-name</i> has more than one method with the given <i>method-name</i> .
	<i>interface</i>	An optional form which when evaluated should yield a COM interface pointer. This is only needed if the definition of the method being called has the <i>interface</i> keyword in its <i>class-spec</i> .

	<i>arg</i>	Arguments to the method (see Section 1.9.1, “Data conversion when calling COM object methods” for details).
Values	<i>values</i>	Values from the method (see Section 1.9.1, “Data conversion when calling COM object methods” for details).
Description	<p>The macro <code>call-com-object</code> invokes the method <i>method-name</i> for the COM class <i>class-name</i>, which should be the type or a supertype of the actual type of <i>object</i>. The <i>args</i> and <i>values</i> are described in detail in Section 1.9.1, “Data conversion when calling COM object methods”.</p> <p>Note that, because this macro requires a COM object, it can only be used by the implementation of that object. All other code should use <code>call-com-interface</code> with the appropriate COM interface pointer.</p>	
Examples	<pre>(call-com-object (my-doc doc-impl move) 0 0) (call-com-object (my-doc doc-impl resize) 100 200)</pre>	
See also	<p><code>with-com-object</code> <code>query-object-interface</code> <code>call-com-interface</code></p>	

check-hresult*Macro*

Summary	Signals an error if a result code indicates a failure.	
Package	<code>com</code>	
Signature	<code>check-hresult</code> <i>hresult</i> <i>function-name</i>	
Arguments	<i>hresult</i>	An integer <code>hresult</code> .
	<i>function-name</i>	A name for inclusion in the error message.

Description The `check-hresult` macro checks the *hresult* and returns if the it is one of the 'succeeded' values, for instance `S_OK` or `S_FALSE`. Otherwise it signals an error of type `com-error`, which will include the *function-name* in its message.

Examples

```
(check-hresult S_OK "test") => nil

(check-hresult E_NOINTERFACE "test")
signals an error mentioning "test"
```

See also

```
succeeded
hresult
hresult-equal
```

co-create-guid

Function

Summary Makes a unique `refguid` object.

Package `com`

Signature `co-create-guid &key register => refguid`

Arguments *register* A generalized boolean.

Values *refguid* A `refguid` object.

Description The function `co-create-guid` makes a new unique `refguid` object. If *register* is true (the default), then the table of known `refguids` is updated.

Examples Make a GUID without registering it in the table of known `ref-guids`:

```
(com:co-create-guid :register nil)
=>
#<REFGUID FOO C76B64AF-969A-4EFF-97BC-6CE2EB65019B>
```

See also `refguid`
`make-guid-from-string`
`com-interface-refguid`
`guid-equal`
`guid-to-string`
`refguid-interface-name`

co-initialize

Function

Summary Initialize the COM library in the current thread.

Package `com`

Signature `co-initialize &optional co-init`

Arguments `co-init` Flags to specify the concurrency model and initialization options for the thread.

Description The function `co-initialize` initializes COM for the current thread. This must be called by every thread that uses COM client or server functions.

The default value of `co-init` is `COINIT_APARTMENTTHREADED`. Other flags are allowed as for the `dwCoInit` argument to `CoInitializeEx`.

Examples `(co-initialize)`

See also `co-uninitialize`

co-task-mem-alloc

Function

Summary Allocates a block of foreign memory for use in COM method argument passing.

Package	<code>com</code>	
Signature	<code>co-task-mem-alloc &key <i>type</i> <i>pointer-type</i> <i>initial-element</i> <i>initial-contents</i> <i>nelems</i> => <i>pointer</i></code>	
Arguments	<i>type</i>	A FLI type specifying the type of the object to be allocated. If <i>type</i> is supplied, <i>pointer-type</i> must not be supplied.
	<i>pointer-type</i>	A foreign pointer type specifying the type of the pointer object to be allocated. If <i>pointer-type</i> is supplied, <i>type</i> must not be supplied.
	<i>initial-element</i>	A keyword setting the initial value of every element in the newly allocated object to <i>initial-element</i> .
	<i>initial-contents</i>	A list of forms which initialize the contents of each element in the newly allocated object.
	<i>nelems</i>	An integer specifying how many copies of the object should be allocated. The default value is 1.
Values	<i>pointer</i>	A pointer to the specified <i>type</i> or <i>pointer-type</i> .
Description	The function <code>co-task-mem-alloc</code> calls the C function <code>CoTaskMemAlloc()</code> to allocate a block of memory. The various arguments are handled in the same way as for the function <code>fli:allocate-foreign-object</code> (see the <i>LispWorks Foreign Language Interface User Guide and Reference Manual</i>).	
Examples	Two ways to allocate memory for an integer: <code>(co-task-mem-alloc :type :int)</code> <code>(co-task-mem-alloc :pointer-type '(:pointer :int))</code>	
See also	<code>co-task-mem-free</code>	

co-task-mem-free*Function*

Summary	Frees a block of foreign memory used in COM method argument passing.	
Package	<code>com</code>	
Signature	<code>co-task-mem-free <i>pointer</i> => <i>pointer2</i></code>	
Arguments	<i>pointer</i>	A foreign pointer for the block to be freed.
Values	<i>pointer2</i>	The same as <i>pointer</i> .
Description	The function <code>co-task-mem-free</code> calls the C function <code>CoTaskMemFree()</code> to free a block of memory. The pointer should not be dereferenced after calling this function.	
Example	<code>(co-task-mem-free ptr)</code>	
See also	<code>co-task-mem-alloc</code>	

co-uninitialize*Function*

Summary	Close the COM library in the current thread.	
Package	<code>com</code>	
Signature	<code>co-uninitialize</code>	
Description	The function <code>co-uninitialize</code> closes the COM library on the current thread. This should be called when COM is no longer required, for instance before exiting the application.	
Examples	<code>(co-uninitialize)</code>	
See also	<code>co-initialize</code>	

com-error

Condition Class

Summary	The condition class used to signal errors from COM.
Package	<code>com</code>
Superclasses	<code>cl:error</code>
Subclasses	<code>com-dispatch-invoke-exception-error</code>
Initargs	<code>:hresult</code> An integer giving the <code>hresult</code> of the error. <code>:function-name</code> Either <code>nil</code> or a string or symbol describing the function that generated the error.
Readers	<code>com-error-hresult</code> <code>com-error-function-name</code>
Description	The class <code>com-error</code> is used by the Lisp COM API when signaling errors that originate as <code>hresult</code> code from COM.
Example	This function silently ignores the <code>E_NOINTERFACE</code> error: <pre>(defun call-ignoring-nointerface-error (function) (handler-bind ((com-error #'(lambda (condition) (when (hresult-equal (com-error-hresult condition) E_NOINTERFACE) (return-from call-ignoring-nointerface-error nil)))))) (funcall function)))</pre>
See also	<code>check-hresult</code> <code>hresult-equal</code> <code>hresult</code>

com-interface*Class*

Summary	The class of all COM interface pointers.
Package	<code>com</code>
Superclasses	<code>fli:foreign-pointer</code>
Description	The class <code>com-interface</code> is used for all COM interface pointers.
Example	<pre>(typep (query-interface ptr 'i-unknown) 'com-interface) => t</pre>
See also	<code>call-com-interface</code>

com-interface-refguid*Function*

Summary	Return the <code>refguid</code> object for a named COM interface.
Package	<code>com</code>
Signature	<code>com-interface-refguid <i>interface-name</i> => <i>refguid</i></code>
Arguments	<i>interface-name</i> A symbol naming a COM interface.
Values	<i>refguid</i> The <code>refguid</code> object matching <i>interface-name</i> .
Description	The function <code>com-interface-refguid</code> returns a <code>refguid</code> object that matches <i>interface-name</i> , which should be a symbol as described in Section 1.3, “The mapping from COM names to Lisp symbols”. This definition of this COM interface must have been converted to Lisp FLI definitions as in Section 1.2.2, “Generating FLI definitions from COM definitions” or Section 3.1, “Including Automation in a Lisp application”.

Examples `(guid-to-string (com-interface-refguid 'i-unknown))`
`=> "00000000-0000-0000-C000-000000000046"`

See also `refguid`
`guid-equal`
`guid-to-string`
`make-guid-from-string`
`refguid-interface-name`

com-object

Class

Summary The ancestor of an COM object implementation classes.

Package `com`

Superclasses `cl:standard-object`

Subclasses `standard-i-unknown`

Description The class `com-object` is the ancestor of all COM object implementation classes. In general, it is more useful to inherit from its subclass `standard-i-unknown`, which provides an implementation of the `i-unknown` interface.

Example For a COM object `my-doc`:
`(typep my-doc 'com-object) => t`

See also `standard-i-unknown`

com-object-destructor

Generic Function

Summary Called when a COM object loses its last interface pointer.

Package `com`

Signature	<code>com-object-destroyer</code> <i>object</i>
Arguments	<i>object</i> A COM object.
Method Signatures	<code>com-object-destroyer</code> (<i>object</i> <code>standard-i-unknown</code>) <code>com-object-destroyer</code> <code>:around</code> (<i>object</i> <code>standard-i-unknown</code>)
Description	<p>The generic function <code>com-object-destroyer</code> is called by the implementation of the class <code>standard-i-unknown</code> at the point where the last COM interface pointer is removed for the object, i.e. where the overall reference count becomes zero. After this, the object is known only to Lisp and is not involved in any COM operations and will be freed as normal by the garbage collector. The built-in primary method specializing on <code>standard-i-unknown</code> does nothing. The built-in around method specializing on <code>standard-i-unknown</code> frees the memory used by the COM interface pointers. Typically, after methods are defined to handle class-specific clean-ups.</p> <p>This function should not be called directly by user code.</p>
Examples	<pre>(defmethod com-object-destroyer :after ((my-doc doc-impl)) (close (document-file my-doc)))</pre>
See also	<code>com-object-initialize</code> <code>standard-i-unknown</code>

com-object-from-pointer

Function

Summary	Return the COM object that implements a particular COM interface pointer.
Package	<code>com</code>

Signature	<code>com-object-from-pointer</code> <i>pointer</i> => <i>object</i>	
Arguments	<i>pointer</i>	A foreign pointer.
Values	<i>object</i>	A COM object or <i>nil</i> .
Description	The function <code>com-object-from-pointer</code> returns the COM object that implements <i>pointer</i> . The value of <i>pointer</i> should be a foreign pointer or COM interface pointer that was created by LispWorks itself and implemented by a subclass of <code>com-object</code> . If <i>pointer</i> is not a known COM interface pointer then <i>nil</i> is returned.	
Example	<code>(com-object-from-pointer my-ptr)</code>	
See also	<code>com-object</code>	

com-object-initialize

Generic Function

Summary	Called when a COM object gets its first interface pointer.	
Package	<code>com</code>	
Signature	<code>com-object-initialize</code> <i>object</i>	
Arguments	<i>object</i>	A COM object.
Method Signatures	<code>com-object-initialize</code> (<i>object</i> <code>standard-i-unknown</code>)	
Description	The generic function <code>com-object-initialize</code> is called by the built-in class <code>standard-i-unknown</code> at the point where the first COM interface pointer is made for the object. Prior to this, the object is known only to Lisp and is not involved in any COM operations. The built-in primary method specializing on <code>standard-i-unknown</code> does nothing.	

This function should not be called directly by user code.

Examples

```
(defmethod com-object-initialize :after
                               ((my-doc doc-impl))
  (ensure-open-document-file my-doc))
```

See also `com-object-destructor`
`standard-i-unknown`

com-object-query-interface

Generic Function

Summary Called by the built in implementation of `query-interface`.

Package `com`

Signature `com-object-query-interface` *object iid*

Arguments *object* A COM object.
iid A GUID foreign pointer.

Method Signatures `com-object-query-interface` (*object* `standard-i-unknown`)
(*iid* `t`)

Description The generic function `com-object-query-interface` is called by the built-in implementation of `query-interface` for the class `standard-i-unknown`. The built-in primary method specializing on `standard-i-unknown` handles the `i-unknown` interface and all the interfaces specified by the `define-com-implementation` form for the class of *object*.

In most cases, there is no need to specialize this generic function for user-defined classes.

This function should not be called directly by user code.

See also `define-com-implementation`
`standard-i-unknown`

create-instance

Function

Summary	Starts the implementation of a remote COM object and returns its interface pointer.	
Package	com	
Signature	<code>create-instance clsid &key unknown-outer clsctx riid errorp => interface-ptr</code>	
Arguments	<i>clsid</i>	A string or a <code>refguid</code> giving a CLSID to create.
	<i>unknown-outer</i>	A COM interface pointer specifying the outer <code>i-unknown</code> if the new instance is to be aggregated.
	<i>clsctx</i>	A CLSCTX value, which defaults to <code>CLSCTX_SERVER</code> .
	<i>riid</i>	An optional <code>refiid</code> giving the name of the COM interface return.
	<i>errorp</i>	A boolean. The default is <code>t</code> .
Values	<i>interface-ptr</i>	A COM interface pointer for <i>riid</i> .
Description	<p>Creates an instance of the COM server associated with <i>clsid</i> and returns an interface pointer for its <i>riid</i> interface. If <i>riid</i> is <code>nil</code>, then <code>i-unknown</code> is used.</p> <p>If the server cannot be started, then an error of type <code>com-error</code> will be signaled if <i>errorp</i> is true, otherwise <code>nil</code> will be returned.</p> <p>If <i>unknown-outer</i> is non-<code>nil</code>, it will be passed as the outer <code>unknown</code> interface to be aggregated with the new instance.</p>	
Notes	To create an <code>i-dispatch</code> interface and set an event handler, you can use <code>create-instance-with-events</code> .	

Example `(create-instance`
`"000209FF-0000-0000-C000-000000000046")`

See also `refguid`
`refiid`
`i-unknown`
`create-object`
`create-instance-with-events`

define-com-implementation*Macro*

Summary Defines an implementation class for a particular set of interfaces.

Package `com`

Signature `define-com-implementation class-name (superclass-name*)`
`(slot-specifier*) class-option*`

Arguments *class-name* A symbol naming the class to define.
superclass-name A symbol naming a superclass to inherit from.
slot-specifier A slot description as used by `defclass`.
class-option An option as used by `defclass`.

Description The macro `define-com-implementation` defines a `standard-class` which is used to implement a COM object. Normal `defclass` inheritance rules apply for slots and Lisp methods.

Each *superclass-name* argument specifies a direct superclass of the new class, which can be another COM implementation class or any other `standard-class` provided that `com-object` is included somewhere in the overall class precedence list. To get the built-in handling for the `i-unknown`

interface, inherit from `standard-i-unknown` (which is the default superclass if no others are specified).

The *slot-specifiers* are standard `defclass` slot definitions.

The *class-options* are standard `defclass` options. In addition the following options are recognized:

```
(:interfaces interface-name*)
```

Each *interface-name* specifies a COM interface that the object will implement. `i-unknown` should not be specified unless you wish to replace the standard implementation provided by `standard-i-unknown`. If more than one *interface-name* is given then all the methods must have different names (except for those which are inherited from a common parent interface).

```
(:inherit-from class-name interface-name*)
```

This indicates that the class will inherit the implementation of all the methods in the interfaces specified by the *interface-names* directly from *class-name*. The *class-name* must be one of the direct or indirect superclasses of the class being defined. Without this option, methods from superclasses are inherited indirectly and can be shadowed in the class being defined. Use of `:inherit-from` allows various internal space-optimizations.

For example, given a COM class `foo-impl` which implements the `i-foo` interface, this definition of `bar-impl`:

```
(define-com-implementation bar-impl (foo-impl)
  ()
  (:interfaces i-foo))
```

will allow methods from `i-foo` to be shadowed whereas this definition:

```
(define-com-implementation bar-impl (foo-impl)
  (:interfaces i-foo)
  (:inherit-from foo-impl i-foo))
```

will result in an error if a method from `i-foo` is redefined for `bar-impl`.

```
(:dont-implement interface-name*)
```

This option tells `standard-i-unknown` that it should not respond to `query-interface` for the given *interface-names* (which should be parents of the interfaces implemented by the class being defined). Normally, `standard-i-unknown` will respond to `query-interface` for a parent interface by returning a pointer to the child interface.

For example, given an interface `i-foo-internal` and sub-interface `i-foo-public`, the following definition

```
(define-com-implementation foo-impl ()
  ()
  (:interfaces i-foo-public))
```

specifies that `foo-impl` will respond to `query-interface` for `i-foo-public` and `i-foo-internal`, whereas the following definition

```
(define-com-implementation foo-impl ()
  (:interfaces i-foo-public)
  (:dont-implement i-foo-internal))
```

specifies that `foo-impl` will respond to `query-interface` for `i-foo-public` only.

Examples

```
(define-com-implementation i-robot-impl ()
  ((tools :accessor robot-tools))
  (:interfaces i-robot)
  )
```

```
(define-com-implementation i-r2d2-impl (i-robot-impl)
  ()
  (:interfaces i-robot i-r2d2)
  )
```

See also `define-com-method`
`standard-i-unknown`

define-com-method

Macro

Summary	The <code>define-com-method</code> macro is used to define a COM method for a particular implementation class.	
Package	<code>com</code>	
Signature	<code>define-com-method</code> <i>method-spec</i> (<i>class-spec</i> <i>arg-spec</i> *) <i>form</i> * <i>method-spec</i> ::= <i>method-name</i> (<i>interface-name</i> <i>method-name</i>) <i>class-spec</i> ::= (<i>this</i> <i>class-name</i> &key <i>interface</i>) <i>arg-spec</i> ::= (<i>parameter-name</i> [<i>direction</i> [<i>pass-style</i>]])	
Arguments	<i>method-spec</i>	Specifies the method to be defined.
	<i>method-name</i>	A symbol naming the method to define.
	<i>interface-name</i>	A symbol naming the interface of the method to define. This is only required if the implementation class <i>class-name</i> has more than one method with the given <i>method-name</i> .
	<i>class-spec</i>	Specifies the implementation class and variables bound to the object with in the <i>forms</i> .
	<i>this</i>	A symbol which will be bound to the COM object whose method is being invoked.
	<i>class-name</i>	A symbol naming the COM implementation class for which this method is defined.

<i>interface</i>	A optional symbol which will be bound to the COM interface pointer whose method is being invoked. Usually this is not needed unless the interface pointer is being passed to some other function in the implementation.
<i>arg-spec</i>	Describes one of the method's arguments.
<i>parameter-name</i>	A symbol which will be bound to that argument's value while the <i>forms</i> are evaluated.
<i>direction</i>	Specifies the direction of the argument, either <code>:in</code> , <code>:out</code> or <code>:in-out</code> . If specified, it must match the definition of the interface. The default is taken from the definition of the interface.
<i>pass-style</i>	Specifies how the argument will be converted to a Lisp value. It can be either <code>:lisp</code> or <code>:foreign</code> , the default is <code>:lisp</code> .
<i>form</i>	Forms which implement the method. The value of the final form is returned as the result of the method.

Description

The macro `define-com-method` defines a COM method that implements the method *method-name* for the COM implementation class *class-name*. The extended *method-spec* syntax is required if *class-name* implements more than one interface with a method called *method-name* (analogous to the C++ syntax `InterfaceName::MethodName`).

The symbol *this* is bound to the instance of the COM implementation class on which the method is being invoked. The symbol *this* is also defined as a local macro (as if by `with-com-object`), which allows the body to invoke other methods on the instance.

If present, the symbol *interface* is bound to the interface pointer on which the method is being invoked.

Each foreign argument is converted to a Lisp argument as specified by the *pass-style*. See Section 1.8.6, “Data conversion in define-com-method” for details.

If an error is to be returned from an Automation method, the function `set-error-info` can be used to provide more details to the caller.

Example

```
(define-com-method (i-robot rotate)
  ((this i-robot-impl)
   (axis :in)
   (angle-delta :in))
  (let ((joint (find-joint axis)))
    (rotate-joint joint))
  S_OK)
```

See also

```
define-com-implementation
set-error-info
set-variant
```

find-clsid

Function

Summary Searches the registry for a GUID or ProgId.

Package `com`

Signature `find-clsid name &optional errorp => refguid`

Arguments

<i>name</i>	A string or a <code>refguid</code> .
<i>errorp</i>	A generalized boolean.

Values

<i>refguid</i>	A <code>refguid</code> .
----------------	--------------------------

Description The function `find-clsid` searches for the supplied GUID or ProgId in the registry.

name can be a string representing a GUID (with or without the curly brackets) or a string containing a ProgId. Otherwise *name* can be a `refguid`, which is simply returned.

If `find-clsid` fails to find the GUID, it either signals an error or returns `nil`, depending on the value of *errorp*. The default value of *errorp* is `t`.

Example To find the GUID of the Explorer ActiveX:

```
(com:find-clsid "Shell.Explorer")
```

get-object

Function

Summary Returns an interface pointer for a named object.

Signature `get-object name &key riid errorp => interface-ptr`

Arguments

<i>name</i>	A string.
<i>riid</i>	An optional <code>refiid</code> giving the name of the COM interface return.
<i>errorp</i>	A boolean. The default value is <code>t</code> .

Values *interface-ptr* A COM interface pointer for *riid*.

Description The function `get-object` finds an existing object named by *name* in the Running Object Table or activates the object if it is not running.

`get-object` returns an interface pointer for the object's *riid* interface. If *riid* is `nil`, then `i-unknown` is used.

If an error occurs, an error of type `com-error` will be signaled if *errorp* is non-`nil`, otherwise `nil` will be returned.

Example If `C:\temp\spreadsheet.xls` is open in Microsoft Excel 2007, then its `WorkBook` interface can be obtained using

```
(get-object "c:\\Temp\\spreadsheet.xls"  
:riid 'i-dispatch)
```

See also `create-instance`
`create-object`
`get-active-object`

guid-equal

Function

Summary `Compares the GUID data in two GUID pointers.`

Package `com`

Signature `guid-equal guid1 guid2 => flag`

Arguments `guid1` A foreign pointer to a GUID object.
`guid2` A foreign pointer to a GUID object.

Values `flag` A boolean, true if `guid1` and `guid2` contain the same GUID data.

Description The function `guid-equal` compares the GUID data in `guid1` and `guid2` and returns true if the data is identical.

Examples

```
(guid-equal (com-interface-refguid 'i-unknown)  
            (com-interface-refguid 'i-dispatch))  
=> nil  
  
(guid-equal (com-interface-refguid 'i-unknown)  
            (make-guid-from-string  
              "00000000-0000-0000-C000-000000000046"))  
=> t
```

See also `refguid`
`com-interface-refguid`
`guid-to-string`
`make-guid-from-string`
`refguid-interface-name`

guid-to-string*Function*

Summary	Converts a GUID to a string of hex characters.	
Package	<code>com</code>	
Signature	<code>guid-to-string <i>guid</i> => <i>guid-string</i></code>	
Arguments	<code><i>guid</i></code>	A foreign pointer to a GUID object.
Values	<code><i>guid-string</i></code>	A string in the standard hex format for GUIDs.
Description	The function <code>guid-to-string</code> converts the data in the <code><i>guid</i></code> to a string of hex characters in the standard-format.	
Example	<pre>(guid-to-string (com-interface-refguid 'i-unknown)) => "00000000-0000-0000-C000-000000000046"</pre>	
See also	<pre>refguid com-interface-refguid guid-equal make-guid-from-string refguid-interface-name</pre>	

hresult*FLI type descriptor*

Summary	The FLI type corresponding to <code>HRESULT</code> in C/C++.	
Package	<code>com</code>	
Signature	<code>hresult</code>	
Description	The <code>hresult</code> type is a signed 32 bit integer. When used as the result type of a COM method, the value <code>E_UNEXPECTED</code> is returned if the COM method body does not return an integer.	

See also `hresult-equal`
`check-hresult`

hresult-equal

Function

Summary Compares one `hresult` to another.

Package `com`

Signature `hresult-equal hres1 hres2 => flag`

Arguments *hres1* An integer `hresult`.
hres2 An integer `hresult`.

Values *flag* A boolean, true if *hres1* and *hres2* are equal.

Description The function `hresult-equal` compares *hres1* and *hres2* and returns true if they represent the same `hresult`. This function differs from the Common Lisp function `eq1` because it handles signed and unsigned versions of each `hresult`.

Example `E_NOTIMPL` is negative, so


```
(eq1 E_NOTIMPL 2147500033)
=> nil

(hresult-equal E_NOTIMPL 2147500033)
=> t
```

See also `hresult`
`check-hresult`
`com-error`

i-unknown

COM Interface Type

Summary The Lisp name for the `IUnknown` COM interface.

Package	<code>com</code>
Description	The symbol <code>i-unknown</code> is the name given to the <code>IUnknown</code> COM interface within Lisp. The name results from the standard mapping described in Section 1.3, “The mapping from COM names to Lisp symbols”.
Examples	<code>(query-interface ptr 'i-unknown)</code>
See also	<code>standard-i-unknown</code> <code>i-dispatch</code>

interface-ref*Macro*

Summary	Accesses a place containing an interface pointer, maintaining reference counts.	
Package	<code>com</code>	
Signature	<code>interface-ref <i>iptr</i> => <i>iptr</i></code> <code>(setf interface-ref) <i>new-value iptr</i> => <i>new-value</i></code>	
Arguments	<i>iptr</i>	A place containing a COM interface pointer or <code>nil</code> .
	<i>new-value</i>	A COM interface pointer or <code>nil</code> .
Description	<code>interface-ref</code> is useful when manipulating a place containing an interface pointer. The <code>setf</code> expander increments the reference count, as if by <code>add-ref</code> , of <i>new-value</i> , unless it is <code>nil</code> . It then decrements the reference count, as if by <code>release</code> , of the existing value in <i>iptr</i> , unless this is <code>nil</code> . Note that this order is important in the case that the new value is the same as the current value. Finally the value of place <i>iptr</i> is set to <i>new-value</i> .	

version-independent-prog-id

The VersionIndependentProgID of the coclass.

Description	Makes an object to contain all the information for class factory registration in the COM runtime. This object should be passed to <code>register-class-factory-entry</code> to perform the registration. This done automatically if you use <code>define-automation-component</code> described in the Chapter 3, “Using Automation”.
Examples	<pre>(make-factory-entry :clsid (make-guid-from-string "7D9EB762-E4E5-11D5-BF02-000347024BE1") :implementation-name 'doc-impl :prog-id "Wordifier.Document.1" :version-independent-prog-id "Wordifier.Document" :friendly-name "Wordifier Document")</pre>
See also	<code>register-class-factory-entry</code>

make-guid-from-string*Function*

Summary	Make a <code>refguid</code> object from a hex string.
Package	<code>com</code>
Signature	<code>make-guid-from-string <i>string</i> &optional <i>interface-name</i> => <i>refguid</i></code>
Arguments	<p><i>string</i> A string in the standard hex format for GUIDs.</p> <p><i>interface-name</i> A symbol naming a COM interface. If non-nil, the <i>refguid</i> will be added to the table of known <code>refguids</code>.</p>
Values	<i>refguid</i> A <code>refguid</code> object matching <i>string</i> .

Description The function `make-guid-from-string` makes a `refguid` object from *string*. If the GUID data matches a known `ref-guid`, then that is returned. Otherwise, a new `refguid` is created and returned. If *interface-name* is non-nil, then the table of known `refguids` is updated. If the GUID is already known under a different name, an error is signaled.

Examples This GUID is a predefined one for `i-unknown`:

```
(refguid-interface-name
 (make-guid-from-string
  "00000000-0000-0000-C000-000000000046"))
=> I-UNKNOWN
```

See also `refguid`
`com-interface-refguid`
`guid-equal`
`guid-to-string`
`refguid-interface-name`

midl

Function

Summary Converts an IDL file into Lisp FLI definitions.

Package `com`

Signature `midl file &key package depth mapping-options output-file load import-search-path`

Arguments *file* A pathname designator giving the name of an IDL file.

package The package in which definitions are created. Defaults to the current package.

depth How many levels of IDL `import` statement to convert to Lisp. This defaults to 0, which means only convert definitions for the IDL file itself. Imported files should be converted

and loaded before the importing file. Some of the standard files are preloaded, so should not be loaded again (see Section 1.2.3, “Standard IDL files”).

mapping-options Allows options to be passed controlling the conversion of individual definitions.

output-file If this is `nil` (the default), the IDL file is compiled in-memory. Otherwise a Lisp `fasl` is produced so the definitions can be reloaded without requiring recompilation. If *output-file* is `t` then the `fasl` is named after the IDL file, otherwise *output-file* is used as a pathname designator to specify the name of the `fasl` file.

load If this is `true` (the default) then any `fasl` produced is loaded after being compiled. Otherwise, the `fasl` must be loaded explicitly with `load`. This argument has no effect if *output-file* is `nil`.

import-search-path

Specifies where to look for files referenced by `import` statements in the IDL. The default value, which is `:default`, causes a search in the same directory as *file*. Otherwise the value should be a list of pathname designators specifying directories to search. After searching using the value of *import-search-path*, `midl` looks in any directory in the list that was set by `midl-set-import-paths` or the `INCLUDE` environment variable, and then the directories that are returned by `midl-default-import-paths`.

Description

This function is used to convert an IDL file into Lisp FLI definitions, which is necessary before the types in the file can be used from the Lisp COM API. See Section 1.3, “The mapping

from COM names to Lisp symbols” for the details on how these FLI definitions are named.

Import paths

When the file that `midl` processes contains import statements (which is the normal case, because at least "unknown.idl" is needed), `midl` looks for the imported file in these directories:

1. The directory in the *import-search-path* argument, or if it is `:default` in the directory of the *file* argument.

Note: you can pass *import-search-path* as `nil` to prevent searching in the directory of *file*. In many cases that is the more useful behavior.

2. The directories in the list that was set by `midl-set-import-paths`, or if it is `:default` the directories in the `INCLUDE` environment variable.

3. The directories in the list that is returned by `midl-default-import-paths`.

The recommended way of getting the standard files to import is to install Windows SDK from microsoft.com. If you install it in the default place, `midl-default-import-paths` should be able to find the right paths. Thus normally installing the Windows SDK is all you need to do to get the standard midl files.

Notes `midl` requires that types like `IDispatch` are declared before they are used.

Examples To compile `myfile.idl` into memory:

```
(midl "myfile.idl")
```

To compile `myfile.idl` to `myfile.ofasl`:

```
(midl "myfile.idl" :output-file t :load nil)
```

To compile `myfile.idl` to `myfile.ofasl` and load it:

```
(midl "myfile.idl" :output-file t)
```

See also `:midl-file`

midl-default-import-paths

Function

Summary Returns the default directories for `midl` to search for imported idl files.

Package `com`

Signature `midl-default-import-paths => paths-list`

Arguments None.

Values *paths-list* A list.

Description The function `midl-default-import-paths` returns the default directories for `midl` to search for imported idl files. See `midl` for more details.

You can call `midl-default-import-paths` to see what paths `midl` is going to use. Microsoft do not actually document where you should be looking for imported files, so there is an element of guessing in `midl-default-import-paths`, but if you install the Windows SDK in the default place it should work.

If the Windows SDK is not installed, `midl-default-import-paths` tries to see if the PlatformSDK (the previous incarnation of the Windows SDK) is installed, and uses it instead.

See also `midl`

midl-set-import-paths

Function

Summary	Sets an internal list for <code>midl</code> to search for imported files.
Package	<code>com</code>
Signature	<code>midl-set-import-paths</code> <i>paths-list</i>
Arguments	<i>paths</i> A list of <i>path-specs</i> (see below), a single <i>path-spec</i> or the keyword <code>:default</code> .
Values	None.
Description	<p>The function <code>midl-set-import-paths</code> sets an internal list for <code>midl</code> to search for imported files. This list overrides the value of the <code>INCLUDE</code> environment variable.</p> <p><i>paths-list</i> can be either a list of <i>path-specs</i>, where a <i>path-spec</i> is either a pathname or a string, or a single <i>path-spec</i>, which is interpreted as a list of this <i>path-spec</i>. It can also be the keyword <code>:default</code>, which resets it so it uses the <code>INCLUDE</code> environment variable.</p>
Notes	In most cases <code>midl</code> should be able to find the imported files in the list that is returned by <code>midl-default-import-paths</code> , so <code>midl-set-import-paths</code> should rarely be useful.
See also	<code>midl</code>

:midl-file

Defsystem Member Type

Summary	The <code>:midl-file</code> defsystem member type can be used to include IDL files in a Lisp system definition.
Package	<code>com</code>

Description	When a file is given the type <code>:midl-file</code> , compiling the system will compile the IDL file to produce a fasl. Loading the system will load this fasl. The <code>:package</code> , <code>:mapping-options</code> and <code>:import-search-path</code> keywords can be specified as for <code>midl</code> .
Examples	<pre>;; Include the file myfile.idl in a system (defsystem my-system () :members (("myfile.idl" :type :midl-file)))</pre>
See also	<code>midl</code>

query-interface

Function

Summary	Attempts to obtain a COM interface pointer for one interface from another.
Package	<code>com</code>
Signature	<code>query-interface</code> <i>interface-ptr</i> <i>iid</i> &key <i>errorp</i> => <i>interface-for-iid</i>
Arguments	<p><i>interface-ptr</i> A COM interface pointer to be queried.</p> <p><i>iid</i> The iid of a COM interface.</p> <p><i>errorp</i> A boolean. The default is <code>t</code>.</p>
Values	<i>interface-for-iid</i> The new COM interface pointer or <code>nil</code> .
Description	<p>The function <code>query-interface</code> function invokes the COM method <code>IUnknown::QueryInterface</code> to attempt to obtain an interface pointer for the given <i>iid</i>. The <i>iid</i> can be a symbol naming a COM interface or a <code>refguid</code> foreign pointer containing its iid.</p> <p>If the <code>IUnknown::QueryInterface</code> returns successfully then the new interface pointer <i>interface-for-iid</i> is returned.</p>

If *errorp* is true, then `nil` is returned if the interface pointer cannot be found, otherwise an error of type `com-error` is signaled.

Example `(query-interface p-foo 'i-bar)`

See also `refguid`
`com-error`
`add-ref`
`release`
`with-temp-interface`
`with-query-interface`

query-object-interface

Macro

Summary Obtains a COM interface pointer for a particular interface from a COM object.

Package `com`

Signature `query-object-interface class-name object iid &key ppv-object => hresult, interface-ptr-for-iid`

Arguments *class-name* The COM object class name of the *object*. This can be a superclass name.
object A COM object to be queried.
iid The iid of a COM interface.
ppv-object If specified, this should be a foreign pointer which will be set to contain the *interface-ptr-for-iid*.

Values *hresult* The `hresult`.
interface-ptr-for-iid The new interface pointer or `nil` if none.

Description The macro `query-object-interface` invokes the COM method `IUnknown::QueryInterface` to attempt to obtain an interface pointer for the given *iid*. The *iid* can be a symbol naming a COM interface or a `refguid` foreign pointer containing its iid.

The first value is the integer `hresult` from the call to `IUnknown::QueryInterface`. If the result indicates success, then *interface-ptr-for-iid* is returned as the second value.

Example

```
(query-object-interface foo-impl p-foo 'i-bar)
```

See also `refguid`
`hresult`

refguid

FLI type descriptor

Summary A FLI type used to refer to GUID objects.

Package `com`

Signature `refguid`

Description The `refguid` type is a pointer to a GUID structure, like the type `REFGUID` in C. In addition, a table of named `refguids` is maintained, using the names chosen when COM interface types are converted to a Lisp FLI definitions by `midl` or parsing a type library.

Example

```
(typep (com-interface-refguid 'i-unknown) 'refguid)
=> t
```

See also `com-interface-refguid`
`guid-equal`
`guid-to-string`
`make-guid-from-string`
`refguid-interface-name`

```
refiid
midl
```

refguid-interface-name

Function

Summary Returns the COM interface name of a `refguid` if known.

Package `com`

Signature `refguid-interface-name refguid => interface-name`

Arguments *refguid* A `refguid` object.

Values *interface-name* A symbol naming the COM interface of *refguid*.

Description Returns a symbol naming the COM interface of *refguid*, which must be a `refguid` object known to Lisp.

Example

```
(refguid-interface-name
 (make-guid-from-string
  "00000000-0000-0000-C000-000000000046"))
=> i-unknown
```

See also `refguid`
`com-interface-refguid`
`guid-equal`
`guid-to-string`
`make-guid-from-string`

refiid

FLI type descriptor

Summary A FLI type used to refer to iids.

Package `com`

Signature	<code>refiid</code>
Description	The <code>refgiid</code> foreign type is a useful converted type for iid arguments to foreign functions. When given a symbol, it looks up the GUID as if by calling <code>com-interface-refguid</code> . Otherwise the value should be a foreign pointer to a GUID structure, which is passed directly without conversion.
Example	Given the definition of <code>print-iid</code> : <pre>(fli:define-foreign-function print-iid ((iid refiid)))</pre> then these two forms are equivalent: <pre>(print-iid 'i-unknown) (print-iid (com-interface-refguid 'i-unknown))</pre>
See also	<code>com-interface-refguid</code> <code>refguid</code>

register-class-factory-entry

Function

Summary	Registers the description of a class factory.
Package	<code>com</code>
Signature	<code>register-class-factory-entry</code> <i>new-factory-entry</i>
Arguments	<i>new-factory-entry</i> A factory entry from <code>make-factory-entry</code> .
Description	Register the factory entry with the COM runtime so that <code>register-server</code> , <code>unregister-server</code> , <code>start-factories</code> and <code>stop-factories</code> will know about the coclass in the factory entry. This is done automatically if you use

`define-automation-component` described in the Chapter 3, “Using Automation”.

Examples

See also `make-factory-entry`
`start-factories`
`stop-factories`
`register-server`
`unregister-server`

register-server

Function

Summary Externally registers all class factories known to Lisp.

Package `com`

Signature `register-server &key clsctx`

Arguments `clsctx` The CLSCTX in which to register the class factory.

Description The `register-server` function updates the Windows registry to contain the appropriate keys for all the class factories registered in the current Lisp image. For Automation components, the type libraries are registered as well. During development, the type library will be found wherever the system definition specified, but after using LispWorks delivery it must be located in the directory containing the application’s executable or DLL.

This function should be called when an application is installed, usually by detecting the `/RegServer` command line argument.

When running on 64-bit Windows, 32-bit LispWorks updates the 32-bit registry view and 64-bit LispWorks updates the 64-

bit registry view. LispWorks does not change the registry reflection settings.

Example

```
(defun start-up-function ()
  (cond ((member "/RegServer"
                 system:*line-arguments-list*
                 :test 'equalp)
         (register-server))
        ((member "/UnRegServer"
                 system:*line-arguments-list*
                 :test 'equalp)
         (unregister-server))
        (t
         (co-initialize)
         (start-factories)
         (start-application-main-loop)))
  (quit))
```

See also

```
unregister-server
register-class-factory-entry
start-factories
stop-factories
set-register-server-error-reporter
```

release

Function

Summary	The <code>release</code> function decrements the reference count of an interface pointer.	
Package	com	
Signature	<code>release</code> <i>interface-ptr</i> => <i>ref-count</i>	
Arguments	<i>interface-ptr</i>	A COM interface pointer.
Values	<i>ref-count</i>	The new reference count.

Description Each COM interface pointer has a reference count which is used by the server to control its lifetime. The function `release` should be called whenever a reference to the interface pointer is being removed. The function invokes the COM method `IUnknown::Release` so the form `(release ptr)` is equivalent to using `call-com-interface` as follows:

```
(call-com-interface (ptr i-unknown release))
```

Example `(release p-foo)`

See also `add-ref`
`interface-ref`
`query-interface`
`with-temp-interface`

`s_ok`

Macro

Summary Compares a result code to the value of `s_ok`.

Package `com`

Signature `s_ok hresult => flag`

Arguments `hresult` An integer `hresult`.

Values `flag` A boolean.

Description The `s_ok` macro checks the `hresult` and returns true if its value is that of the constant `S_OK`.

Examples `(S_OK S_OK) => t`
`(S_OK S_FALSE) => nil`
`(S_OK E_NOINTERFACE) => nil`

See also `succeeded`
`hresult`
`hresult-equal`
`check-hresult`

server-can-exit-p

server-in-use-p

Functions

Summary Predicates for whether a COM server is in use or can exit.

Package `com`

Signature `server-can-exit-p => result`

Signature `server-in-use-p => result`

Arguments None.

Values `result` A boolean.

Description The function `server-in-use-p` returns true when the COM server is in use, which means one or more of the following:

1. There are live objects other than the class factories.
2. Any of the class factories has more than one reference.
3. The server is locked by a client call to the COM method `IClassFactory::LockServer`.

The function `server-can-exit-p` returns true if the server can exit, which means that the server is not in use (that is, `(not (server-in-use-p))` returns `t`), and also that there are no other "working processes", which means that all other processes except the one that calls `server-can-exit-p` are "Internal servers" (see `mp:process-run-function`).

The main purpose of `server-can-exit-p` is to be the *exit-function* for `automation-server-top-loop`, either as the default or called from a supplied *exit-function*.

See also `automation-server-top-loop`

set-automation-server-exit-delay

Function

Summary Sets the *exit-delay* used by `automation-server-top-loop`.

Package `com`

Signature `set-automation-server-exit-delay exit-delay`

Arguments *exit-delay* A non-negative real number specifying a time in seconds.

Description The function `set-automation-server-exit-delay` sets the *exit-delay* which is used by `automation-server-top-loop` to delay exiting once the server is unused.

`set-automation-server-exit-delay` can be called both before and after `automation-server-top-loop`, and can be used repeatedly after `automation-server-top-loop` was called to dynamically change the *exit-delay*. The setting persists over saving and delivering an image, so it can be used in the delivery script too.

See also `automation-server-top-loop`

set-register-server-error-reporter

Function

Summary Allows control over the reporting, logging or debugging of failures from `register-server` and `unregister-server`.

Package	<code>com</code>
Signature	<code>set-register-server-error-reporter <i>func</i> => <i>func</i></code>
Arguments	<i>func</i> A function or a fbound symbol.
Values	<i>func</i> A function or a fbound symbol.
Description	<p>The function <code>set-register-server-error-reporter</code> sets up a function <i>func</i> that is called to report when calls and automatic calls to <code>register-server</code> or <code>unregister-server</code> via the system-defined entry points of a DLL fail.</p> <p><i>func</i> should be a function of two arguments.</p> <p>The automatic calls happen when registering/unregistering a LispWorks DLL that was saved or delivered with the keyword <code>:com</code> in its <code>:dll-exports</code> (see “Making a COM DLL with LispWorks” on page 2). If such a call fails, <i>func</i> is invoked with the name of the function that failed (currently either <code>register-server</code> or <code>unregister-server</code>) and the condition. <i>func</i> should report the failure in a useful way, which would normally mean logging it in a place where you can inspect it later.</p>
Notes	<ol style="list-style-type: none"> 1. After <i>func</i> returns or throws out, the automatic call returns with an appropriate failure code, and the code that tries to register (that is, the program that called <code>DllRegisterServer</code> or <code>DllUnregisterServer</code>) should normally print an error too. For example, <code>regsvr32</code> would raise a dialog by default. However, this dialog will not contain any information about what failed inside Lisp. 2. By default (that is, if you do not call <code>set-register-server-error-reporter</code>) any such error is simply printed to standard output.

3. *func* can force entering the debugger using `cl:invoke-debugger`, which may sometimes be useful during development.

See also `register-server`
`unregister-server`

standard-i-unknown

Class

Summary	A complete implementation of the <code>i-unknown</code> interface.
Package	<code>com</code>
Superclasses	<code>com-object</code>
Subclasses	<code>standard-i-dispatch</code> <code>standard-i-connection-point-container</code>
Initargs	<code>:outer-unknown</code> An optional interface pointer to the outer unknown interface if this object is <i>aggregated</i> .
Description	<p>The class <code>standard-i-unknown</code> provides a complete implementation of the <code>i-unknown</code> interface.</p> <p>The class provides a reference count for the object which calls the generic function <code>com-object-initialize</code> when the object is given a reference count and <code>com-object-destroyer</code> when it becomes zero again. These generic functions can be specialized to perform initialization and cleanup operations.</p> <p>The class also provides an implementation of <code>query-interface</code> which calls the generic function <code>com-object-query-interface</code>. The default method handles <code>i-unknown</code> and all the interfaces specified by the</p>

`define-com-implementation` form for the class of the object.

There is support for *aggregation* via the `:outer-unknown` initarg, which is also passed by built-in class factory implementation.

Example

Inheriting from a non-COM class requires `standard-i-unknown` to be mentioned explicitly:

```
(define-com-implementation doc-impl
  (document-mixin
   standard-i-unknown)
  ()
  (:interfaces i-doc))
```

See also

```
define-com-implementation
standard-i-dispatch
standard-i-connection-point-container
com-object-initialize
com-object-destructor
com-object-query-interface
com-object
i-unknown
```

start-factories

Function

Summary	Starts all the registered class factories.
Package	<code>com</code>
Signature	<code>start-factories &optional <i>clsctx</i></code>
Arguments	<code><i>clsctx</i></code> The CLSCTX in which to start the factories.
Description	The <code>start-factories</code> function starts all the registered class factories in the given <code><i>clsctx</i></code> , which defaults to <code>CLSCTX_LOCAL_SERVER</code> . This function should be called once

when a COM server application starts if it has externally registered class factories.

See also `register-class-factory-entry`
`stop-factories`
`register-server`
`unregister-server`
`co-initialize`

stop-factories

Function

Summary Stops all the registered class factories.

Package `com`

Signature `stop-factories`

Description The `stop-factories` function stops all the registered class factories. This function should be called once before a COM server application exits if it has externally registered class factories.

See also `register-class-factory-entry`
`start-factories`
`register-server`
`unregister-server`
`co-uninitialize`

succeeded

Macro

Summary Checks an `hresult` for success.

Package `com`

Signature `succeeded hresult => flag`

Arguments	<i>hresult</i>	An integer <i>hresult</i> .
Values	<i>flag</i>	A boolean.
Description	The <code>succeeded</code> macro checks the <i>hresult</i> and returns true if the it is one of the 'succeeded' values, for instance <code>S_OK</code> or <code>S_FALSE</code> .	
Examples	<pre>(succeeded S_OK) => t (succeeded E_NOINTERFACE) => nil</pre>	
See also	<pre>check-hresult hresult hresult-equal s_ok</pre>	

unregister-server*Function*

Summary	Externally unregisters all class factories known to Lisp.	
Package	<code>com</code>	
Signature	<code>unregister-server</code>	
Description	<p>The <code>unregister-server</code> function updates the Windows registry to remove the appropriate keys for all the class factories registered in the current Lisp image. For Automation components, the type libraries are unregistered as well.</p> <p>This function should be called when an application is uninstalled, usually by detecting the <code>/UnRegServer</code> command line argument.</p> <p>When running on 64-bit Windows, 32-bit LispWorks updates the 32-bit registry view and 64-bit LispWorks updates the 64-bit registry view. LispWorks does not change the registry reflection settings.</p>	

Example

```
(defun start-up-function ()
  (cond ((member "/UnRegServer"
                 system:*line-arguments-list*
                 :test 'equalp)
         (unregister-server))
        ((member "/RegServer"
                 system:*line-arguments-list*
                 :test 'equalp)
         (register-server))
        (t
         (co-initialize)
         (start-factories)
         (start-application-main-loop)))
  (quit))
```

See also

```
register-server
register-class-factory-entry
start-factories
stop-factories
set-register-server-error-reporter
```

with-com-interface

Macro

Summary Used to simplify invocation of several methods from a particular COM interface pointer.

Package `com`

Signature `with-com-interface disp interface-ptr form* => values`
`disp ::= (dispatch-function interface-name)`

Arguments *disp* The names of the dispatch function and interface.

dispatch-function A symbol which will be defined as a local macro, as if by `macrolet`. The macro can be used by the *forms* to invoke the methods on *interface-ptr*.

	<i>interface-name</i>	A symbol which names the COM interface. It is not evaluated.
	<i>interface-ptr</i>	A form which is evaluated to yield a COM interface pointer that implements <i>interface-name</i> .
	<i>form</i>	A form to be evaluated.
Values	<i>values</i>	The values returned by the last <i>form</i> .
Description	<p>When the macro <code>with-com-interface</code> evaluates the <i>forms</i>, the local macro <i>dispatch-function</i> can be used to invoked the methods for the COM interface <i>interface-name</i>, which should be the type or a supertype of the actual type of <i>interface-ptr</i>.</p> <p>The <i>dispatch-function</i> macro has the following signature:</p> <p><i>dispatch-function</i> <i>method-name</i> <i>arg*</i> => <i>values</i></p> <p>where</p> <p><i>method-name</i> A symbol which names the method. It is not evaluated.</p> <p><i>arg</i> Arguments to the method (see Section 1.7.1, “Data conversion when calling COM methods” for details).</p> <p><i>values</i> Values from the method (see Section 1.7.1, “Data conversion when calling COM methods” for details).</p>	
Example	<p>This example invokes the COM method <code>GetTypeInfo</code> in the interface <code>IDispatch</code>.</p> <pre>(defun get-type-info (disp tinfo &key (locale LOCALE_SYSTEM_DEFAULT)) (multiple-value-bind (hres typeinfo) (with-com-interface (call-disp i-dispatch) disp (call-disp get-type-info tinfo locale)) (check-hresult hres 'get-type-info) typeinfo))</pre>	

See also `call-com-interface`

with-com-object *Macro*

Summary	Used to simplify invocation of several methods from a given COM object.	
Package	<code>com</code>	
Signature	<code>with-com-object <i>disp object form*</i> => <i>values</i></code> <code><i>disp</i> ::= (<i>dispatch-function class-name &key interface</i>)</code>	
Arguments	<i>disp</i>	The names of the dispatch function and object class.
	<i>dispatch-function</i>	A symbol which will be defined as a macro, as if by <code>macrolet</code> . The macro can be used by the <i>forms</i> to invoke the methods on <i>object</i> .
	<i>class-name</i>	A symbol which names the COM implementation class. It is not evaluated.
	<i>interface</i>	An optional form which when evaluated should yield a COM interface pointer. This is only needed if the definition of the methods being called have the <i>interface</i> keyword in their <i>class-specs</i> .
	<i>object</i>	A form which is evaluated to yield a COM object.
	<i>form</i>	A form to be evaluated.
Values	<i>values</i>	The values returned by the last <i>form</i> .
Description	When the macro <code>call-com-object</code> evaluates the <i>forms</i> , the local macro <i>dispatch-function</i> can be used to invoked the methods for the COM class <i>class-name</i> , which should be the type or a supertype of the actual type of <i>object</i> .	

The *dispatch-function* macro has the following signature:

dispatch-function* *method-spec* *arg** => *values

***method-spec* ::= *method-name* | (*interface-name* *method-name*)**

where

method-spec Specifies the method to be called. It is not evaluated.

method-name A symbol naming the method to call.

interface-name A symbol naming the interface of the method to call. This is only required if the implementation class *class-name* has more than one method with the given *method-name*.

arg Arguments to the method (see Section 1.9.1, “Data conversion when calling COM object methods” for details).

values Values from the method (see Section 1.9.1, “Data conversion when calling COM object methods” for details).

Note that, because *with-com-object* requires a COM object, it can only be used by the implementation of that object. All other code should use *with-com-interface* with the appropriate COM interface pointer.

Example

```
(with-com-object (call-my-doc doc-impl) my-doc
  (call-my-doc move 0 0)
  (call-my-doc resize 100 200))
```

See also

call-com-object
define-com-method
with-com-interface

with-temp-interface

Macro

Summary	Used to simplify reference counting for a COM interface pointer.	
Package	com	
Signature	<code>with-temp-interface (var) <i>interface-ptr form*</i> => values</code>	
Arguments	<i>var</i>	A variable which is bound to <i>interface-ptr</i> while the <i>forms</i> are evaluated.
	<i>interface-ptr</i>	A form which is evaluated to yield a COM interface pointer.
	<i>form</i>	A form to be evaluated.
Values	<i>values</i>	The values returned by the last <i>form</i> .
Description	When the macro <code>with-temp-interface</code> evaluates the <i>forms</i> , the variable <i>var</i> is bound to the value of <i>interface-ptr</i> . When control leaves the body (whether directly or due to a non-local exit), <code>release</code> is called with this interface pointer.	
Example	This example invokes the COM method <code>GetDocumentation</code> in the interface <code>ITypeInfo</code> on an interface pointer which must be released after use. <pre>(defun get-tinfo-member-documentation (disp tinfo member-id) (with-temp-interface (typeinfo) (get-type-info disp tinfo) (call-com-interface (typeinfo i-type-info get-documentation) member-id)))</pre>	
See also	<code>release</code> <code>with-query-interface</code>	

with-query-interface

Macro

Summary	Used to simplify reference counting when querying a COM interface pointer.	
Package	com	
Signature	with-query-interface <i>disp</i> interface-ptr <i>form*</i> => <i>values</i> disp ::= (<i>punknown</i> <i>interface-name</i> &key <i>errorp</i> <i>dispatch</i>)	
Arguments	<i>punknown</i>	A variable which is bound to the queried interface pointer while the <i>forms</i> are evaluated.
	<i>interface-name</i>	A symbol which names the COM interface. It is not evaluated.
	<i>errorp</i>	A boolean indicating whether an error should be signaled if <i>interface-name</i> is not implemented by <i>interface-ptr</i> .
	<i>dispatch</i>	A symbol which will be defined as a local macro, as if by <code>macrolet</code> as if by <code>with-com-interface</code> . The macro can be used by the <i>forms</i> to invoke the methods on <i>punknown</i> .
	<i>interface-ptr</i>	A form which is evaluated to yield a COM interface pointer to query.
	<i>form</i>	A form to be evaluated.
Values	<i>values</i>	The values returned by the last <i>form</i> .
Description	The macro <code>with-query-interface</code> calls <code>query-interface</code> to find an interface pointer for <i>interface-name</i> from the existing COM interface pointer <i>interface-ptr</i> . While evaluates the <i>forms</i> , the variable <i>punknown</i> is bound to the queried pointer and the pointer is released when control leaves the body (whether directly or due to a non-local exit).	

If *errorp* is true, then *punknown* is bound to `nil` if the interface pointer cannot be found, otherwise an error of type `com-error` is signaled.

If *dispatch* is specified, then a local macro is created as if by `with-com-interface` to invoke COM interface methods on *punknown*.

Example

This example invokes the methods on an `i-bar` interface pointer queried from an existing interface pointer.

```
(with-query-interface (p-bar i-bar
                      :dispatch call-bar)
  p-foo
  (call-bar bar-init)
  (call-bar bar-print))
```

See also

```
query-interface
release
with-temp-interface
```

2 *COM Reference Entries*

3

Using Automation

3.1 Including Automation in a Lisp application

This section describes how to load Automation and generate any FLI definitions needed to use it.

3.1.1 Loading the modules

Before using any of the LispWorks Automation APIs, you need to load the module using

```
(require "automation")
```

3.1.2 Generating FLI definitions from COM definitions

Automation components and interfaces that are to be used by the Automation API must be placed in a type library using suitable tools. In some cases, this type library will be supplied as part of the DLL or executable containing the component.

Some of the Automation APIs described in this chapter require you to convert the definitions in the type library into FLI definitions. This is done by compiling and loading a system definition that references the library with the options `:type :midl-type-library-file`. The names in the type library are

converted to Lisp symbols as specified in “The mapping from COM names to Lisp symbols” on page 3

Note: this is not required by all the APIs, for example see “Calling Automation methods without a type library” on page 92 and “A simple implementation of a single Automation interface” on page 97.

3.1.3 Reducing the size of the converted library

Suppose you have a `defsystem` system definition form that references a library: that is, a system member has options `:type` `:midl-type-library-file` as described in “Generating FLI definitions from COM definitions” on page 89.

For this member, the option `:com` can be added to specify whether all the COM functionality is required. The keyword can take these values:

<code>t</code>	Analyze and generate all the required code for calling and implementing the interfaces from the type library. This is the default value.
<code>nil</code>	Analyze but do not generate any code for calling or implementing COM interfaces from the type library. It is still possible to call Automation methods.
<code>:not-binary</code>	Analyze but do not generate any code for calling or implementing COM interfaces from the type library. It is still possible to call Automation methods and implement <i>dispinterfaces</i> in the type library, but not dual or COM interfaces.

Using the value `nil` or `:not-binary` generates much smaller code and is therefore much faster. However, it is never obligatory to use the option `:com`.

Use `:com nil` when the application calls Automation interfaces from the type library but does not implement any of them or need to call any methods from dual interfaces using `call-com-interface`.

Use `:com :not-binary` when the application implements only *dispinterfaces* from the library. This is typically required for implementing *sink* interfaces for use with connection points.

For an example see

```
(example-edit-file "com/ole/simple-container/defsys")
```

3.2 Starting a remote Automation server

A remote Automation server is started from Lisp by using its coclass name, CLSID or ProgID. The macro `with-coclass` can be used to make an instance of an automation server from its coclass name for the duration of its body. The function `create-object` can be used to start an automation server given its CLSID or ProgID. The function `create-instance-with-events` can be used to start an automation server and set its event handler. The function `get-active-object` can be used to look for a registered running instance of a coclass in the system Running Object Table.

3.3 Calling Automation methods

Automation methods can be called either with or without a compiled type library. In both cases, arguments and return values are converted according to the types specified by the method's definition.

3.3.1 Calling Automation methods using a type library

To use this approach, you must have the type library available at compile-time (see "Generating FLI definitions from COM definitions" on page 89). Information from the type library is built into your application, which makes method calling more efficient. However, it also makes it less dynamic, because the library at the time the application is run must match.

There are three kinds of Automation method, each of which is called using macros designed for the purpose.

- Ordinary methods are called using the macros `call-dispatch-method` and `with-dispatch-interface`. If there is no Automation method with the given method name, then a property getter with the same name is called if it exists, otherwise an error is signaled. The `setf` form of `call-dispatch-method` can be used to call property setter methods.
- Property getter methods are called using the macro `call-dispatch-get-property`.

- Property setter methods are called using the macros `call-dispatch-put-property` or the `setf` form of `call-dispatch-get-property`.

To use these macros, you need to specify the interface name, the method name, a COM interface pointer for the `i-dispatch` interface and suitable arguments. The interface and method names are given as symbols named as in Section 1.3 on page 3 and the COM interface pointer is a foreign pointer of type `com-interface`. In all the macros, the *args* and *values* are as specified in the Section 3.3.3.

The `with-dispatch-interface` macro is useful when several methods are being called with the same COM interface pointer, because it establishes a local macro that takes just the method name and arguments.

3.3.2 Calling Automation methods without a type library

This approach is useful if the type library is not available at compile time or you want to allow methods to be called dynamically without knowing the interface pointer type at compile-time. It can be less efficient than using the approach in Section 3.3.1, but is often the simplest approach, especially if the Automation component was written to be called from a language like Visual Basic.

There are three kinds of Automation method, each of which is called using functions designed for the purpose.

- Ordinary methods are called using the function `invoke-dispatch-method`. If there is no Automation method with the given method name, then a property getter with the same name is called if it exists, otherwise an error is signaled. The `setf` form of `invoke-dispatch-method` can be used to call property setter methods.
- Property getter methods are called using the function `invoke-dispatch-get-property`.
- Property setter methods are called either using the function `invoke-dispatch-put-property` or the `setf` form of `invoke-dispatch-get-property`.

To use these functions, you need to specify a COM interface pointer for the `i-dispatch` interface, the method name and suitable arguments. The method

name is given as a string or integer and the COM interface pointer is a foreign pointer of type `com-interface`. In all the functions, the *args* and *values* are as specified in the Section 3.3.3.

3.3.3 Data conversion when calling Automation methods

The arguments and return values to Automation methods are restricted to a small number of simple types, which map to Lisp types as follows:

Table 3.1 Automation types, VT codes and their corresponding Lisp types

Automation type	VT code	Lisp type
null value	VT_NULL	the symbol <code>:null</code>
empty value	VT_EMPTY	the symbol <code>:empty</code>
SHORT	VT_I2	integer
LONG	VT_I4	integer
FLOAT	VT_R4	single-float
DOUBLE	VT_R8	double-float
CY	VT_CY	not supported
DATE	VT_DATE	not supported
BSTR	VT_BSTR	string
IDispatch*	VT_DISPATCH	FLI (<code>:pointer i-dispatch</code>)
SCODE	VT_ERROR	integer
VARIANT_BOOL	VT_BOOL	nil or t
VARIANT*	VT_VARIANT	recursively convert
IUnknown*	VT_UNKNOWN	FLI (<code>:pointer i-unknown</code>)
DECIMAL	VT_DECIMAL	not supported
BYTE	VT_UI1	integer
SAFEARRAY	VT_ARRAY	array
dynamic	dynamic	lisp-variant

When an Automation argument is a `lisp-variant` object, its type is used to set the VT code. See `make-lisp-variant` and `set-variant`.

In and *in-out* parameters are passed as positional arguments in the calling forms and *out* and *in-out* parameters are returned as additional values. If there is an argument with the `retval` attribute then it is returned as the first value.

Optional parameters can be passed as `:not-specified` if they are not needed. Alternatively, they can be omitted if all remaining optional arguments are also omitted.

3.3.4 Using collections

The macro `do-collection-items` can be used to iterate over the items or an interface that implements the Collection protocol. If the collection items are interface pointers, they must be released when not needed.

For example, to iterate over the `Table` objects from the `Tables` collection of a `MyDocument` interface pointer

```
(with-temp-interface (tables)
  (call-dispatch-get-property
    (doc my-document tables))
  (do-collection-items (table tables)
    (inspect-the-table table)
    (release table)))
```

3.3.5 Using connection points

Event *sink* interfaces can be connected and disconnected using the functions `interface-connect` and `interface-disconnect`.

For example, the following macro connects a sink interface pointer *event-handler* to a source of `i-clonable-events` events *clonable* for the duration of its body.

```
(defmacro handling-clonable-events ((clonable event-handler)
                                   &body body)
  (lw:with-unique-names (cookie)
    (lw:rebinding (clonable event-handler)
      `(let ((,cookie nil))
         (unwind-protect
          (progn
            (setq ,cookie
                  (interface-connect ,clonable
                                     'i-clonable-events
                                     ,event-handler))
              ,@body)
          (when ,cookie
            (interface-disconnect ,clonable
                                  'i-clonable-events
                                  ,cookie))))))
```

3.3.6 Error handling

When an Automation server returns an error code, the calling macros such as `call-dispatch-method` signal an error of type `com-error`. The error message will contain the *source* and *description* fields from the error.

For example, if `pp` is a dispatch pointer to `i-test-suite-1`:

```
CL-USER 184 > (call-dispatch-method
               (pp nil i-test-suite-1 fx))
"in fx"
;; implementation running
Error: COM IDispatch::Invoke Exception Occurred (0 "fx") : foo
  1 (abort) Return to level 0.
  2 Return to top loop level 0.

Type :b for backtrace, :c <option number> to proceed, or :? for
other options
```

3.4 Implementing Automation interfaces in Lisp

This section describes two techniques for implementing Automation interfaces in Lisp. The choice of technique usually depends on whether you are implementing a complete server or a simple event sink. The section then describes other kinds of interfaces that can be implemented and how to report errors to the caller of a method.

3.4.1 A complete implementation of an Automation server

In the case where you are designing an set of COM interfaces and implementing a server to support them, you need to make a complete implementation in Lisp. This allows several Automation interfaces to be implemented by a single class and also supports *dual* interfaces.

The implementation defines an appropriate class, inheriting from the class `standard-i-dispatch` to obtain an implementation of the COM interface `i-dispatch`. This implementation of `i-dispatch` will automatically invoke the appropriate COM method.

For *dual* interfaces, the methods should be defined in the same way as described for COM interfaces in Section 1.8 on page 13.

For *dispinterfaces*, the methods should be implemented using the macro `define-dispinterface-method` or by a specialized method of the generic function `com-object-dispinterface-invoke`.

To implement an Automation interface in Lisp with `standard-i-dispatch`, you need the following:

1. A type library for the component, converted to Lisp as specified in Section 3.1 on page 89.
2. A COM object class defined with `define-automation-component` or `define-automation-collection`, specifying the coclass or interface(s) to implement.
3. Implementations of the methods using `define-com-method`, `define-dispinterface-method` or `com-object-dispinterface-invoke`.
4. For an out-of-process Automation component, either use `automation-server-main` or have registration code which calls `register-server` and `unregister-server`, typically after checking the result of `automation-server-command-line-action` or explicitly checking the command line for arguments `/RegServer` and `/UnRegServer`.
5. Initialization code which either calls `automation-server-top-loop` or `automation-server-main`, or calls `co-initialize` and `start-factories` in a thread that will be processing Windows messages (for instance a CAPI thread).

3.4.2 A simple implementation of a single Automation interface

In the case where you are implementing a single dispinterface that was designed by someone else, for example an *event sink*, you can usually avoid needing to parse a type library or define a class to implement the interface.

Instead, you implement a dispinterface using the class `simple-i-dispatch` by doing the following:

1. Obtain an interface pointer that will provide type information for the component, to be used as the *related-dispatch* argument in the call to the function `query-simple-i-dispatch-interface`. In the case where you are implementing an event sink, the source interface pointer will usually do this.
2. Optionally, define a class with `defclass` inheriting from `simple-i-dispatch`. The class `simple-i-dispatch` can be used itself if no special callback object is required.
3. Implement an *invoke-callback* that selects and implements the methods of the interface.
4. Define initialization code which calls `co-initialize`, obtains the *related-dispatch* from step 1, makes an instance of the COM object class defined in step 2 with the *invoke-callback* from step 3, obtains its interface pointer by calling `query-simple-i-dispatch-interface` (passing the *related-dispatch*) and attaches this interface pointer to the appropriate sink in the *related-dispatch* (for example using connection point functions such as `interface-connect`). This must all be done in a thread that will be processing Windows messages (for instance a CAPI thread).

3.4.3 Implementing collections

Interfaces that support the Collection protocol can be implemented using the macro `define-automation-collection`. This defines a subclass of `standard-automation-collection`, which implements the minimal set of collection methods and calls Lisp functions to provide the items. If the collection items are interface pointers, appropriate reference counting must be observed.

See the example files here:

```
(example-edit-file "com/automation/collections/")
```

3.4.4 Implementing connection points

Lisp implementations can act as *event sources* via a built-in implementation of the `IConnectionPointContainer` interface, which `define-automation-component` provides if *source* interfaces are specified. A built-in implementation of `IConnectionPoint` handles connections for each interface and the macro `do-connections` can be used to iterate over the connections when firing the events.

3.4.5 Reporting errors

Classes defined using `define-automation-component` allow extended error information to be returned for all Automation methods. Within the body of a `define-com-method` definition, the function `set-error-info` can be called to describe the error. In addition, this function returns the value of `DISP_E_EXCEPTION`, which can be returned directly as the `hresult` from the method.

For example:

```
(define-com-method (i-test-suite-1 fx)
  ((this c-test-suite-1))
  (print "in fx")
  (set-error-info :description "foo"
                 :iid 'i-test-suite-1
                 :source "fx"))
```

3.4.6 Registering a running object for use by other applications

If other applications need to be able to find one of your running objects from its coclass, then call `register-active-object` to register an interface pointer for the object in the system Running Object Table. Call `revoke-active-object` to remove the registration.

3.4.7 Automation of a CAPI application

For an example of how to implement an Automation server that controls a CAPI application, see the file:

```
(example-edit-file "com/automation/capi-application/build")
```

3.5 Examples of using Automation

Several complete examples are provided in the `examples` subdirectory of your LispWorks library.

A simple Automation application:

```
(example-edit-file "com/automation/capi-application/readme.txt")
```

```
(example-edit-file "com/automation/cl-smtp/clsmtpl-build")
```

Controlling an Automation application:

```
(example-edit-file "com/automation/capi-application/readme.txt")
```

```
(example-edit-file "com/automation/cl-smtp/clsmtpl-test")
```

Getting events from COM interfaces:

```
(example-edit-file "com/automation/events/ie-events")
```

```
(example-edit-file "com/automation/capi-application/readme.txt")
```

3 *Using Automation*

4

Automation Reference Entries

This chapter documents Automation functionality.

com-dispatch-invoke-exception-error

Condition Class

Summary	The condition class used to signal Automation exceptions.
Package	<code>com</code>
Superclasses	<code>com-error</code>
Initargs	None
Description	The class <code>com-dispatch-invoke-exception-error</code> is used by the LispWorks COM API when Automation signals an exception (<code>DISP_E_EXCEPTION</code>).
See also	<code>com-dispatch-invoke-exception-error-info</code>

com-dispatch-invoke-exception-error-info *Function*

Summary	Retrieves information stored in a <code>com-dispatch-invoke-exception-error</code> .	
Package	<code>com</code>	
Signature	<code>com-dispatch-invoke-exception-error-info</code> <i>condition</i> <i>fields</i> => <i>field-values</i>	
Arguments	<i>condition</i>	A <code>com-dispatch-invoke-exception-error</code> .
	<i>fields</i>	A list of keywords as specified below.
Values	<i>field-values</i>	A list.
Description	<p>The function <code>com-dispatch-invoke-exception-error-info</code> retrieves information about the exception from a <code>com-dispatch-invoke-exception-error</code> object. The keywords in <i>fields</i> are used to select which information is returned in <i>field-values</i>, which is a list of values corresponding to each keyword in <i>fields</i>.</p>	

The following keyword are supported in *fields*:

<code>:code</code>	The error code.
<code>:source</code>	The source of the error.
<code>:description</code>	The description of the error.
<code>:help-file</code>	The help file for the error.
<code>:help-context</code>	The help context for the error.

Example

```
(handler-case
  (com:invoke-dispatch-method counter "Run")
  (com:com-dispatch-invoke-exception-error (condition)
    (destructuring-bind (code description)
      (com:com-dispatch-invoke-exception-error-info
        condition
        '(:code :description))
      (format *error-output*
        "Run failed with code ~D, description ~S."
        code
        description))))
```

See also `com-dispatch-invoke-exception-error`

call-dispatch-get-property Macro

Summary Calls an Automation property getter method from a particular interface.

Package `com`

Signature `call-dispatch-get-property spec arg* => values`
spec ::= (dispinterface-ptr dispinterface-name method-name)

Arguments *spec* The interface pointer and a specification of the method to be called.

dispinterface-ptr A form which is evaluated to yield a COM `i-dispatch` interface pointer.

dispinterface-name

A symbol which names the Automation interface. It is not evaluated.

method-name A symbol which names the property getter method. It is not evaluated.

arg Arguments to the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).

Values	<i>values</i>	Values from the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).
Description	<p>The <code>call-dispatch-get-property</code> macro is used to invoke an Automation property getter method from Lisp. The <i>dispinterface-ptr</i> should be a COM interface pointer for the <code>i-dispatch</code> interface. The appropriate Automation property getter method, chosen using <i>dispinterface-name</i> and <i>method-name</i>, is invoked after evaluating each <i>arg</i>. The <i>args</i> must be values that are suitable for the method and of types compatible with Automation. The values returned are as specified by the method signature. In general, property getter methods take no arguments and return the value of the property, but see Section 3.3.3, “Data conversion when calling Automation methods” for more details.</p> <p>There is also <code>setf</code> expander for <code>call-dispatch-get-property</code>, which can be used as an alternative to the <code>call-dispatch-put-property</code> macro.</p>	
Example	<p>For example, in order to get and set the <code>width</code> property of a <code>MyDocument</code> interface pointer</p> <pre>(call-dispatch-get-property (doc my-document width)) (setf (call-dispatch-get-property (doc my-document width)) 10)</pre>	
See also	<p><code>call-dispatch-put-property</code> <code>call-dispatch-method</code></p>	

call-dispatch-method

Macro

Summary Calls an Automation method from a particular interface.

Package	com	
Signature	<code>call-dispatch-method <i>spec arg*</i> => <i>values</i></code> <code><i>spec</i> ::= (<i>dispinterface-ptr dispinterface-name method-name</i>)</code>	
Arguments	<i>spec</i>	The interface pointer and a specification of the method to be called.
	<i>dispinterface-ptr</i>	A form which is evaluated to yield a COM <code>i-dispatch</code> interface pointer.
	<i>dispinterface-name</i>	A symbol which names the Automation interface. It is not evaluated.
	<i>method-name</i>	A symbol which names the method. It is not evaluated.
	<i>arg</i>	Arguments to the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).
Values	<i>values</i>	Values from the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).
Description	<p>The <code>call-dispatch-method</code> macro is used to invoke an Automation method from Lisp. The <i>dispinterface-ptr</i> should be a COM interface pointer for the <code>i-dispatch</code> interface. The appropriate Automation method, chosen using <i>dispinterface-name</i> and <i>method-name</i>, is invoked after evaluating each <i>arg</i>. The <i>args</i> must be values that are suitable for the method and of types compatible with Automation. The values returned are as specified by the method signature. See Section 3.3.3, “Data conversion when calling Automation methods” for more details. If there is no Automation method with the given <i>method-name</i>, then a property getter with the same name is called if it exists, otherwise an error is signaled. The</p>	

`setf` form of `call-dispatch-method` can be used to call property setter methods.

Example For example, in order to invoke the `ReFormat` method of a `MyDocument` interface pointer

```
(call-dispatch-method (doc my-document re-format))
```

See also `with-dispatch-interface`
`call-dispatch-get-property`
`call-dispatch-put-property`

call-dispatch-put-property

Macro

Summary Calls an Automation property setter method from a particular interface.

Package `com`

Signature `call-dispatch-put-property spec arg* => values`
`spec ::= (dispinterface-ptr dispinterface-name method-name)`

Arguments *spec* The interface pointer and a specification of the method to be called.

dispinterface-ptr A form which is evaluated to yield a COM `i-dispatch` interface pointer.

dispinterface-name

A symbol which names the Automation interface. It is not evaluated.

method-name A symbol which names the property getter method. It is not evaluated.

arg Arguments to the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).

Values *values* Values from the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).

Description The `call-dispatch-put-property` macro is used to invoke an Automation property setter method from Lisp. The *dispatch-ptr* should be a COM interface pointer for the `i-dispatch` interface. The appropriate Automation property setter method, chosen using *dispinterface-name* and *method-name*, is invoked after evaluating each *arg*. The *args* must be values that are suitable for the method and of types compatible with Automation. The values returned are as specified by the method signature. In general, property setter methods take one argument (the new value) and return the no values, but see Section 3.3.3, “Data conversion when calling Automation methods” for more details.

There is also `setf` expander for `call-dispatch-get-property`, which can be used as an alternative to the `call-dispatch-put-property` macro.

Example For example, in order to set the `width` property of a `MyDocument` interface pointer

```
(call-dispatch-put-property
  (doc my-document width)
  10)
```

See also `call-dispatch-get-property`
`call-dispatch-method`

com-object-dispinterface-invoke

Generic Function

Summary A generic function called by `IDisppatch::Invoke` when there is no defined *dispinterface* method.

Package `com`

Signature	<code>com-object-dispinterface-invoke</code> <i>com-object method-name method-type args</i> <code>=> value</code>	
Arguments	<i>com-object</i>	A COM object whose method is being invoked.
	<i>method-name</i>	A string naming the method to be called.
	<i>method-type</i>	A keyword specifying the type of method being called.
	<i>args</i>	A vector containing the arguments to the method.
Description	The generic function <code>com-object-dispinterface-invoke</code> is called by <code>IDispatch::Invoke</code> when there is no method defined using <code>define-dispinterface-method</code> .	
	Methods can be written for <code>com-object-dispinterface-invoke</code> , specializing on an Automation implementation class and implementing the method dispatch based on <i>method-name</i> and <i>method-type</i> .	
	The <i>method-name</i> argument is a string specifying the name of the method as given by the method declaration in the IDL or type library. The <i>method-type</i> argument, has one of the following values:	
	<code>:get</code>	when invoking a property getter method.
	<code>:put</code>	when invoking a property setter method.
	<code>:method</code>	when invoking a normal method.
	The arguments to the method are contained in the vector <i>args</i> , in the order specified by the method declaration in the type library. For <i>in</i> and <i>in-out</i> arguments, the corresponding element of <i>args</i> contains the argument value converted to the type specified by the method declaration and then converted to Lisp objects as specified in Section 3.3.3, “Data conversion when calling Automation methods”. For <i>out</i> and <i>in-out</i> arguments, the corresponding element of <i>args</i> should be set by the	

method to contain the value to be returned to the caller and will be converted to an automation value as specified in Section 3.3.3, “Data conversion when calling Automation methods”.

The *value* should be a value which can be converted to the appropriate return type as the primary value of the method and will be converted to an automation value as specified in Section 3.3.3, “Data conversion when calling Automation methods”. It is ignored for methods that are declared as returning void.

Notes When using `com-object-dispinterface-invoke`, it is not possible to distinguish between invocations of the same method name for different interfaces when *com-object* implements several interfaces. If this is required, then the method must be defined with `define-dispinterface-method`.

Example `(example-edit-file`
 `"com/ole/simple-container/owc-spreadsheet")`

See also `define-dispinterface-method`

create-instance-with-events

Function

Summary A convenience function which combines `create-instance` and `set-i-dispatch-event-handler`.

Package `com`

Signature `create-instance-with-events clsid event-handler &rest args`
 `&key event-object => interface, list`

Arguments *clsid* A string or a `refguid` giving a CLSID to create.

event-handler A function of four arguments.

	<i>event-object</i>	A Lisp object.
Values	<i>interface</i>	An <i>i-dispatch</i> interface.
	<i>sinks</i>	A list of objects representing the connections made.
Description	<p>The function <code>create-instance-with-events</code> is a convenience function which starts an <i>i-dispatch</i> interface and sets an event handler.</p> <p>It first calls <code>create-instance</code> with <i>clsid</i> and all the keyword arguments except the <i>event-object</i>. It defaults the <code>create-instance</code> argument <i>riid</i> to the value <i>i-dispatch</i>.</p> <p>It then calls <code>set-i-dispatch-event-handler</code> on the resulting interface, passing <i>event-handler</i>, <i>event-object</i> and <i>clsid</i> (as the <i>coclass</i>).</p> <p><i>interface</i> is the interface started, and <i>sinks</i> is the result of <code>set-i-dispatch-event-handler</code>.</p>	
Examples	<code>(example-edit-file "com/automation/events/ie-events")</code>	
See also	<code>create-instance</code> <code>set-i-dispatch-event-handler</code>	

create-object*Function*

Summary	Create an instance of a coclass.	
Package	<code>com</code>	
Signature	<code>create-object &key <i>clsid</i> <i>progid</i> <i>clsctx</i> => <i>interface-ptr</i></code>	
Arguments	<i>clsid</i>	A string giving a CLSID to create.
	<i>progid</i>	A string giving a ProgID to create.

	<i>clsctx</i>	A CLSCTX value, which defaults to <code>CLSCTX_SERVER</code> .
Values	<i>interface-ptr</i>	An <code>i-dispatch</code> interface pointer.
Description		Creates an instance of a coclass and returns its <code>i-dispatch</code> interface pointer. The coclass can be specified directly by using the <i>clsid</i> argument or indirectly using the <i>progid</i> argument, which will locate the CLSID from the registry.
Examples		The following are equivalent ways of creating an Microsoft Word application object: <pre>(create-object :progid "Word.Application.8") (create-object :clsid "000209FF-0000-0000-C000-000000000046")</pre>
See also	<code>with-coclass</code>	

define-automation-collection

Macro

Summary		Defines an implementation class for an Automation component that supports the Collection protocol.
Package	<code>com</code>	
Signature		<code>define-automation-collection</code> <i>class-name</i> (<i>superclass-name</i> *) (<i>slot-specifier</i> *) <i>class-option</i> *
Arguments	<i>class-name</i>	A symbol naming the class to define.
	<i>superclass-name</i>	A symbol naming a superclass to inherit from.
	<i>slot-specifier</i>	A slot description as used by <code>defclass</code> .
	<i>class-option</i>	An option as used by <code>defclass</code> .

Description The macro `define-automation-collection` defines a `standard-class` which is used to implement an Automation component that supports the Collection protocol. Normal `defclass` inheritance rules apply for slots and Lisp methods. Each *superclass-name* argument specifies a direct superclass of the new class, which can be any `standard-class` provided that `standard-automation-collection` is included somewhere in the overall class precedence list. This standard class provides a framework for the collection class.

slot-specifiers are standard `defclass` slot definitions.

class-options are standard `defclass` options. In addition the following options are recognized:

`(:interface interface-name)`

This option is required. The component will implement the *interface-name*, which must be an Automation Collection interface, containing (at least) the standard properties `Count` and `_NewEnum`. The macro will define an implementation of these methods using information from the instance of the class to count and iterate.

`(:item-method item-method-name*)`

When specified, a COM method named *item-method-name* will be defined that will look up items using the `item-lookup-function` from the instance.

If not specified, the method will be called `Item`. For Collections which do not have an item method, pass `nil` as the *item-method-name*.

Example

See also `define-automation-component`
`standard-automation-collection`

define-automation-component

Macro

Summary	Define an implementation class for a particular Automation component.
Package	<code>com</code>
Signature	<code>define-automation-component</code> <i>class-name</i> (<i>superclass-name*</i>) (<i>slot-specifier*</i>) <i>class-option*</i>
Arguments	<i>class-name</i> A symbol naming the class to define. <i>superclass-name</i> A symbol naming a superclass to inherit from. <i>slot-specifier</i> A slot description as used by <code>defclass</code> . <i>class-option</i> An option as used by <code>defclass</code> .
Description	<p>The macro <code>define-automation-component</code> defines a <code>standard-class</code> which is used to implement an Automation component. Normal <code>defclass</code> inheritance rules apply for slots and Lisp methods.</p> <p>Each <i>superclass-name</i> argument specifies a direct superclass of the new class, which can be any <code>standard-class</code> provided that certain standard classes are included somewhere in the overall class precedence list. These standard classes depend on the other options and provide the default superclass list if none is specified. The following standard classes are available:</p> <ul style="list-style-type: none">• <code>standard-i-dispatch</code> is always needed and provides a complete implementation of the <code>i-dispatch</code> interface, based on the type information in the type library.

- `standard-i-connection-point-container` is needed if there are any source interfaces specified (via the `:coclass` or `:source-interfaces` options). This provides a complete implementation of the Connection Point protocols.

slot-specifiers are standard `defclass` slot definitions.

class-options are standard `defclass` options. In addition the following options are recognized:

(`:coclass` *coclass-name*)

coclass-name is a symbol specifying the name of a coclass. If this option is specified then a class factory will be registered for this coclass, to create an instance of *class-name* when another application requires it. The component will implement the interfaces specified in the coclass definition and the default interface will be returned by the class factory.

Exactly one of `:coclass` and `:interfaces` must be specified.

(`:interfaces` *interface-name**)

Each *interface-name* specifies an Automation interface that the object will implement. The `i-unknown` and `i-dispatch` interfaces should not be specified because their implementations are automatically inherited from `standard-i-dispatch`. No class factory will be registered for *class-name*, so the only way to make instances is from with Lisp by calling `make-instance`.

Exactly one of `:coclass` and `:interfaces` must be specified.

(:source-interfaces *interface-name**)

Each *interface-name* specifies a source interface on which the object allows connections to be made. If the :coclass option is also specified, then the interfaces flagged with the source attribute are used as the default for the :source-interfaces option.

When there are event interfaces, the component automatically implements the IConnectionPointContainer interface. The supporting interfaces IEnumConnectionPoints, IConnectionPoint and IEnumConnections are also provided automatically.

(:extra-interfaces *interface-name**)

Each *interface-name* specifies a COM interface that the object will implement, in addition to the interfaces implied by the :coclass option. This allows the object to implement other interfaces not mentioned in the type library.

(:coclass-reusable-p *reusable*)

If *reusable* is true (the default), then the server running the component can receive requests from more than one application. If *reusable* is nil, then the server will receive requests only from the application that started it and the Operating System will start a new instance of the server if required. For more details, see REGCLS_MULTIPLEUSE and REGCLS_SINGLEUSE in MSDN.

`(:type-library type-library-name)`

type-library-name is a symbol specifying the name of a type library, mapped from the name given by the "library" statement in the IDL. If this option is specified then an error is signaled if the names used in the `:coclass`, `:interfaces` or `:source-interfaces` class options are not defined by *type-library-name*.

Use `define-com-method`, `define-dispinterface-method` or `com-object-dispinterface-invoke` to define methods in the interfaces implemented by the component. See also Section 1.8.4, "Unimplemented methods".

Example

```
(define-automation-component c-test-suite-1 ()
  ((prop3 :initform nil)
   (interface-4-called :initform nil))
  (:coclass test-suite-component)
  )
```

See also

```
define-com-method
define-dispinterface-method
com-object-dispinterface-invoke
standard-i-dispatch
standard-i-connection-point-container
define-automation-collection
```

define-dispinterface-method

Macro

Summary

The `define-dispinterface-method` macro is used to define a *dispinterface* method.

Package

`com`

Signature

```
define-dispinterface-method method-spec (class-spec .  
lambda-list) form* => value
```

method-spec ::= *method-name* | (*interface-name* *method-name*)

class-spec ::= (*this* *class-name*)

Arguments	<i>method-spec</i>	Specifies the method to be defined.
	<i>method-name</i>	A symbol naming the method to define.
	<i>interface-name</i>	A symbol naming the interface of the method to define. This is only required if the implementation class <i>class-name</i> has more than one method with the given <i>method-name</i> .
	<i>class-spec</i>	Specifies the implementation class and variables bound to the object with in the <i>forms</i> .
	<i>this</i>	A symbol which will be bound to the COM object whose method is being invoked.
	<i>class-name</i>	A symbol naming the COM implementation class for which this method is defined.
	<i>lambda-list</i>	A simple lambda list. That is, a list of parameter names.
	<i>form</i>	Forms which implement the method. The value of the final form is returned as the result of the method.
	<i>value</i>	The value to be returned to the caller.

Description

The macro `define-dispinterface-method` defines a *dispinterface* method that implements the method *method-name* for the Automation implementation class *class-name*. The extended *method-spec* syntax is required if *class-name* implements more than one interface with a method called *method-name* (analogous to the C++ syntax `InterfaceName::MethodName`).

The symbol *this* is bound to the instance of the Automation implementation class on which the method is being invoked.

The number of parameter in *lambda-list* must match the declaration in the type library. Each *in* and *in-out* parameter is bound to the value passed to `IDispatch::Invoke`, converted to the type specified by the method declaration and then converted to Lisp objects as specified in Section 3.3.3, “Data conversion when calling Automation methods”. For missing values the value of the parameter is `:not-found`. For *out* and *in-out* arguments, the corresponding parameter should be set by the forms to contain the value to be returned to the caller and will be converted to an automation value as specified in Section 3.3.3, “Data conversion when calling Automation methods”.

The *value* should be a value which can be converted to the appropriate return type as the primary value of the method and will be converted to an automation value as specified in Section 3.3.3, “Data conversion when calling Automation methods”. It is ignored for methods that are declared as returning void.

Notes	The <code>define-com-method</code> macro should be used to implement methods in <i>dual</i> interfaces.
See also	<code>define-com-method</code> <code>com-object-dispinterface-invoke</code>

disconnect-standard-sink

Function

Summary	Releases a standard sink object, stopping the events.	
Package	<code>com</code>	
Signature	<code>disconnect-standard-sink</code> <i>sink</i> => <i>result</i>	
Arguments	<i>sink</i>	A standard sink object.
Values	<i>result</i>	<code>t</code> or <code>nil</code> .

Description The function `disconnect-standard-sink` releases a standard sink object. This is one of the objects in the list returned by `set-i-dispatch-event-handler` which represents a connection it made.

`disconnect-standard-sink` stops the events that pass through *sink*.

result is `t` if the sink was released.

See also `create-instance-with-events`
 `set-i-dispatch-event-handler`

do-collection-items

Macro

Summary Iterates over the items of an Automation Collection.

Package `com`

Signature `do-collection-items (item collection) form*`

Arguments

<i>item</i>	A symbol bound to each item in the collection in turn.
<i>collection</i>	A form which is evaluated to yield a COM <code>i-dispatch</code> interface pointer that implements the collection protocol.
<i>form</i>	A form to be evaluated.

Description The `do-collection-items` macro executes each *form* in turn, with *item* bound to each item of the *collection*.

 Note that for collections whose items are interface pointers, the *forms* must arrange for each pointer to be released when no longer needed. The *collection* should be a COM interface pointer for an `i-dispatch` interface that implements the Collection protocol. The items are converted to Lisp as specified

in Section 3.3.3, “Data conversion when calling Automation methods”.

Example For example, to iterate over the `Table` objects from the `Tables` collection of a `MyDocument` interface pointer

```
(with-temp-interface (tables)
  (call-dispatch-get-property
    (doc my-document tables))
  (do-collection-items (table tables)
    (inspect-the-table table)
    (release table)))
```

See also `call-dispatch-method`

do-connections

Macro

Summary Iterates over the sinks for a given Automation component object.

Package `com`

Signature `do-connections ((sink interface-name &key dispatch automation-dispatch) container) form*`

Arguments *sink* A symbol which will be bound to each sink interface pointer.

interface-name A symbol naming the sink interface.

dispatch A symbol which will be bound to a local macro that invokes a method from the sink interface as if by `with-com-interface`.

automation-dispatch

A symbol which will be bound to a local macro that invokes a method from the sink interface as if by `with-dispatch-interface`.

container An instance of a component class that has *interface-name* as one of its source interfaces.

form A form to be evaluated.

Description The macro `do-connections` provides a way to iterate over all the sink interface pointers for the source interface *interface-name* in the connection point container *container*. The *container* must be a subclass of `standard-i-connection-point-container`. Each *form* is evaluated in turn with *sink* bound to each interface pointer. If *dispatch* is given, it is defined as a local macro invoking the COM interface *interface-name* as if by `with-com-interface`. If *automation-dispatch* is given, it is defined as a local macro invoking the Automation interface *interface-name* as if by `with-dispatch-interface`.

Within the scope of `do-connections` you can call the local function `discard-connection` which discards the connection currently bound to *sink*. This is useful when an error is detected on that connection, for example when the client has terminated. The signature of this local function is

```
discard-connection &key release
```

release is a boolean defaulting to false. If *release* is true then `release` is called on *sink*.

Example Suppose there is a source interface `i-clonable-events` with a method `on-cloned`. The following function can be used to invoke this method on all the sinks of an instance of a `clonable-component` class:

```
(defun fire-on-cloned (clonable-component)
  (do-connections ((sink i-clonable-events
                       :dispatch call-clonable)
                  clonable-component)
    (call-clonable on-cloned value)))
```

See also `with-dispatch-interface`
`with-com-interface`
`standard-i-connection-point-container`

find-component-tlb*Function*

Summary Returns the path of the type library associated with a component name.

Package `com`

Signature `find-component-tlb name &key version min-version max-version => path`

Arguments

<i>name</i>	A string.
<i>version</i>	A string or <code>nil</code> .
<i>min-version</i>	A string or <code>nil</code> .
<i>max-version</i>	A string or <code>nil</code> .

Values *path* A string or `nil`.

Description The function `find-component-tlb` returns the path of the type library associated with the component *name*.
name should be the name of a component (either a ProgID or a GUID).
 If *version* is supplied, `find-component-tlb` finds only this version of the type library.
 If *min-version* or *max-version*, or both of these, are supplied, they restrict which version of the type library can be found.
 Each of *version*, *min-version* and *max-version*, if supplied, should be a string. The string should contain either one hexadecimal number or two hexadecimal numbers separated by a

dot. The first number is the major version, the second is the minor version, which defaults to 0.

If *version* is not supplied, then `find-component-tlb` preferentially finds the the library version specified in the registry for the component (if any) if it fits the specification by *max-version* and/or *min-version*, otherwise it finds the earliest version in the range specified by *min-version* and *max-version*.

`find-component-tlb` returns `nil` if it fails to find the type library within the specified version constraints.

See also `:midl-type-library-file`

find-component-value

Function

Summary Searches the registry for values associated with a component.

Package `com`

Signature `find-component-value name key-name => result, root`

Arguments *name* A string.
key-name A string or a keyword.

Values *result* A Lisp object.
root A keyword.

Description The function `find-component-value` searches the Windows registry for values associated with a component.

name should be the name of a component (either a ProgID or a GUID).

key-name should name a registry key. If it is a string, it should match the key name in the registry. Otherwise *key-name* can be one of the following keywords:

`:library` Returns the library that implements the component (if any)

`:inproc-server32`
As for `:library`

`:local-server32`
Returns the executable that implements the component (if any)

`:version` Returns the version

`:prog-id` Returns the ProgID

`:version-independent-prog-id`
Returns the version-independent ProgID

`:type-lib` Returns the GUID of the type library

`find-component-value` returns the value *result* associated with the given *key-name* in the registry for component *name*. If a value is found., then there is a second returned value *root* which is either `:local-machine` or `:user`, indicating the branch of the registry in which the value was found.

`find-component-value` simply returns `nil` if it fails to find the information.

When running on 64-bit Windows, 32-bit LispWorks looks in the 32-bit registry view and 64-bit LispWorks looks in the 64-bit registry view. LispWorks does not change the registry reflection settings.

Examples `(com:find-component-value "shell.explorer" :version)`

get-active-object

Function

Summary Looks for a registered running instance of a coclass.

Signature `get-active-object &key clsid progid riid errorp => interface-ptr`

Arguments	<i>clsid</i>	A string or a <code>refguid</code> giving a CLSID to create.
	<i>progid</i>	A string giving a ProgID to create.
	<i>riid</i>	An optional <code>refiid</code> giving the COM interface name to return.
	<i>errorp</i>	A boolean. The default is <code>t</code> .
Values	<i>interface-ptr</i>	A COM interface pointer for <i>riid</i> .
Description		<p>Looks for a registered running instance of a coclass in the system Running Object Table and returns its <i>riid</i> interface pointer if any. If <i>riid</i> is <code>nil</code>, then <code>i-unknown</code> is used.</p> <p>The coclass can be specified directly by using the <i>clsid</i> argument or indirectly using the <i>progid</i> argument, which will locate the CLSID from the registry.</p> <p>If <i>errorp</i> is true, then an error is signaled if no instances are running. Otherwise <code>nil</code> is returned if no instances are running.</p>
Example		<pre>(get-active-object :progid "Excel.Application" :riid 'i-dispatch)</pre>
See also	<code>get-object</code>	

get-error-info

Function

Summary	Retrieves the error information for the current Automation method.
Package	<code>com</code>
Signature	<code>get-error-info &key errorp fields => field-value*</code>

Arguments	<i>errorp</i>	A boolean. If true and an error occurs while retrieving the error information, then an error of type <code>com-error</code> is signaled. Otherwise <code>nil</code> is returned.
	<i>fields</i>	A list of keywords specifying the error information fields to return.
Values	<i>field-value*</i>	Values corresponding to the <i>fields</i> argument.
Description		The function <code>get-error-info</code> allows the various components of the error information to be retrieved for the last Automation method called. The <i>fields</i> should be a list of the following keywords, to specify which fields of the error information should be returned:
		<p><code>:iid</code> A <code>refguid</code> object.</p> <p><code>:source</code> A string specifying the ProgID.</p> <p><code>:description</code> A string describing the error.</p> <p><code>:help-file</code> A string giving the help file's path.</p> <p><code>:help-context</code> An integer giving the help context id.</p> <p>A <i>field-value</i> will be returned for each <i>field</i> specified. The <i>field-value</i> will be <code>nil</code> if the <i>field</i> does not have a value.</p>
Example		<pre>(multiple-value-bind (source description) (get-error-info :fields '(:source :description)) (error "Failed with '~A' in ~A" description source))</pre>
See also		<pre>set-error-info call-dispatch-method com-error</pre>

get-i-dispatch-name*Function*

Summary Returns the foreign name of an `i-dispatch` interface.

Package	<code>com</code>
Signature	<code>get-i-dispatch-name <i>i-dispatch</i> => <i>name</i></code>
Arguments	<i>i-dispatch</i> An <code>i-dispatch</code> interface.
Values	<i>name</i> A string.
Description	The function <code>get-i-dispatch-name</code> returns the foreign name of an <code>i-dispatch</code> interface. That is, it obtains the first return value of <code>ITypeInfo::GetDocumentation</code> .
Example	To implement code like this: <pre>If TypeOf objMap.Selection Is Pushpin Then ... </pre> you would need something like: <pre>(if (equalp (com:get-i-dispatch-name selection) "PushPin") ...)</pre>
See also	<code>print-i-dispatch-methods</code> <code>i-dispatch</code> <code>create-object</code> <code>create-instance-with-events</code> “Starting a remote Automation server” on page 91

get-i-dispatch-source-names

Function

Summary	Returns the source names associated with an <code>i-dispatch</code> interface.
Package	<code>com</code>
Signature	<code>get-i-dispatch-source-names <i>i-dispatch</i> &key <i>all</i> <i>coclass</i> => <i>source-names</i></code>

Arguments	<i>i-dispatch</i>	An <code>i-dispatch</code> interface.
	<i>all</i>	A generalized boolean, default value <code>false</code> .
	<i>coclass</i>	The coclass to use, or <code>nil</code> .
Values	<i>source-names</i>	A list.
Description	<p>The function <code>get-i-dispatch-source-names</code> returns the source names that are associated with the <code>i-dispatch</code> interface <i>i-dispatch</i>, which will be used by <code>set-i-dispatch-event-handler</code>.</p> <p><i>coclass</i> and <i>all</i> are as described for <code>set-i-dispatch-event-handler</code>.</p>	
Notes	<p>If you need to call <code>set-i-dispatch-event-handler</code> repeatedly, then it is most efficient to call <code>get-i-dispatch-source-names</code> once and pass the result <i>source-names</i> to <code>set-i-dispatch-event-handler</code>. This is because <code>set-i-dispatch-event-handler</code> itself calls <code>get-i-dispatch-source-names</code> if its <i>source-names</i> argument is <code>nil</code>.</p>	
See also	<code>set-i-dispatch-event-handler</code>	

i-dispatch*COM Interface Type*

Summary	The Lisp name for the <code>i-dispatch</code> COM interface.	
Package	<code>com</code>	
Description	<p>The symbol <code>i-dispatch</code> is the name given to the <code>i-dispatch</code> COM interface within Lisp. The name results from the standard mapping described in Section 1.3, “The mapping from COM names to Lisp symbols”.</p>	

Examples `(query-interface ptr 'i-dispatch)`

See also `i-unknown`
`standard-i-dispatch`

interface-connect

Function

Summary Connects a sink interface pointer to the source of events in another COM interface pointer.

Package `com`

Signature `interface-connect interface-ptr iid sink-ptr &key errorp => cookie`

Arguments

- interface-ptr* A COM interface pointer that provides the source interface *iid*.
- iid* The iid of the source interface to be connected. The iid can be a symbol naming the interface or a `refguid` foreign pointer.
- sink-ptr* A COM interface that will receive the events for the *iid*.
- errorp* A boolean. When false, errors connecting the *sink-ptr* will cause `nil` to be returned. Otherwise an error of type `com-error` will be signaled.

Values *cookie* An integer cookie associated with this connection.

Description Connects the COM interface *sink-ptr* to the connection point in *interface-ptr* that is named by *iid*.

Example Suppose there is an interface pointer `clonable` which provides a source interface `i-clonable-events`, then the fol-

lowing form can be used to connect an implementation of this source interface `sink`:

```
(setq cookie
      (interface-connect clonable
                        'i-clonable-events
                        sink))
```

See also `interface-disconnect`
`refguid`
`com-error`

interface-disconnect

Function

Summary	Disconnect a sink interface pointer from the source of events in another COM interface pointer.	
Package	<code>com</code>	
Signature	<code>interface-disconnect &key <i>interface-ptr</i> <i>iid</i> <i>cookie</i> &key <i>errorp</i> => <i>flag</i></code>	
Arguments	<i>interface-ptr</i>	A COM interface pointer that provides the source interface <i>iid</i> .
	<i>iid</i>	The iid of the source interface to be disconnected. The iid can be a symbol naming the interface or a <code>refguid</code> foreign pointer.
	<i>cookie</i>	The integer cookie associated with the connection to be disconnected.
	<i>errorp</i>	A boolean. When false, errors disconnecting the <i>cookie</i> will cause <code>nil</code> to be returned. Otherwise an error of type <code>com-error</code> will be signaled.
Values	<i>flag</i>	A boolean, true for successful disconnection.

Description Disconnects the connection for *cookie* from the connection point in *interface-ptr* that matches *iid*.

Example Suppose there is an interface pointer `clonable` which provides a source interface `i-clonable-events`, then the following form can be used to disconnect an implementation of this source interface with cookie `cookie`:

```
(interface-disconnect clonable
                      'i-clonable-events
                      cookie)
```

See also `interface-connect`
`refguid`
`com-error`

lisp-variant

Type

Summary An object that contains a type and a value.

Package `com`

Accessors `lisp-variant-type`
`lisp-variant-value`

Description A `lisp-variant` is an object that contains a type and a value. The type and value are as described for the function `set-variant`.

See also `make-lisp-variant`
`set-variant`

invoke-dispatch-get-property

Function

Summary Call a dispatch property getter method from an interface pointer.

Package	<code>com</code>
Signature	<code>invoke-dispatch-get-property</code> <i>dispinterface-ptr</i> <i>name</i> &rest <i>args</i> => <i>values</i>
Arguments	<p><i>dispinterface-ptr</i> An Automation interface pointer.</p> <p><i>name</i> A string or integer.</p> <p><i>args</i> Arguments passed to the method.</p>
Values	<i>values</i> Values returned by the method.
Description	<p>The function <code>invoke-dispatch-get-property</code> is used to invoke an Automation property getter method from Lisp without needing to compile a type library as part of the application. This is similar to using</p> <pre>Dim var as Object Print #output, var.Prop</pre> <p>in Microsoft Visual Basic and contrasts with the macro <code>call-dispatch-get-property</code> which requires a type library to be compiled.</p> <p>The <i>dispinterface-ptr</i> should be a COM interface pointer for the <code>i-dispatch</code> interface. The appropriate Automation method, chosen using <i>name</i>, which is either a string naming the method or the integer id of the method. The <i>args</i> are converted to Automation values and are passed as the method's <i>in</i> and <i>in-out</i> parameters in the order in which they appear. The <i>values</i> returned consist of the primary value of the method (if not void) and the values of any <i>out</i> or <i>in-out</i> parameters. See Section 3.3.3, "Data conversion when calling Automation methods" for more details.</p> <p>There is also <code>setf</code> expander for <code>invoke-dispatch-get-property</code>, which can be used as an alternative to the <code>call-dispatch-put-property</code> macro.</p>

Example For example, in order to get and set the `width` property of an interface pointer in the variable `doc`:

```
(invoke-dispatch-get-property doc "Width")  
  
(setf (invoke-dispatch-get-property  
      doc "Width")  
      10)
```

See also `invoke-dispatch-method`
`invoke-dispatch-put-property`
`call-dispatch-get-property`

invoke-dispatch-method

Function

Summary Call a dispatch method from an interface pointer.

Package `com`

Signature `invoke-dispatch-method` *dispinterface-ptr* *name* &rest *args* => *values*

Arguments *dispinterface-ptr* An Automation interface pointer.
name A string or integer.
args Arguments passed to the method.

Values *values* Values returned by the method.

Description The function `invoke-dispatch-method` is used to invoke an Automation method from Lisp without needing to compile a type library as part of the application. This is similar to using

```
Dim var as Object  
var.Method(1,2)
```

in Microsoft Visual Basic and contrasts with the macro `call-dispatch-method` which requires a type library to be compiled.

The *dispinterface-ptr* should be a COM interface pointer for the `i-dispatch` interface. The appropriate Automation method, chosen using *name*, which is either a string naming the method or the integer id of the method. The *args* are converted to Automation values and are passed as the method's *in* and *in-out* parameters in the order in which they appear. The *values* returned consist of the primary value of the method (if not void) and the values of any *out* or *in-out* parameters. See Section 3.3.3, "Data conversion when calling Automation methods" for more details. If there is no Automation method with the given name, then a property getter with the same name is called if it exists, otherwise an error is signaled. The `setf` form of `invoke-dispatch-method` can be used to call property setter methods.

Example For example, in order to invoke the `ReFormat` method of an interface pointer in the variable `doc`:

```
(invoke-dispatch-method doc "ReFormat")
```

See also `invoke-dispatch-get-property`
`invoke-dispatch-put-property`
`call-dispatch-method`

invoke-dispatch-put-property

Function

Summary Call a dispatch property setter method from an interface pointer.

Package `com`

Signature `invoke-dispatch-put-property dispinterface-ptr name &rest args => values`

Arguments *dispinterface-ptr* An Automation interface pointer.
name A string or integer.

	<i>args</i>	Arguments passed to the method.
Values	<i>values</i>	Values returned by the method.
Description	<p>The function <code>invoke-dispatch-put-property</code> is used to invoke an Automation property setter method from Lisp without needing to compile a type library as part of the application. This is similar to using</p> <pre>Dim var as Object var.Prop = 2</pre> <p>in Microsoft Visual Basic and contrasts with the macro <code>call-dispatch-put-property</code> which requires a type library to be compiled.</p> <p>The <i>dispinterface-ptr</i> should be a COM interface pointer for the <i>i-dispatch</i> interface. The appropriate Automation method, chosen using <i>name</i>, which is either a string naming the method or the integer id of the method. The <i>args</i> are converted to Automation values and are passed as the method's <i>in</i> and <i>in-out</i> parameters in the order in which they appear. The new value of the property should be the last argument. The <i>values</i> returned consist of the primary value of the method (if not void) and the values of any <i>out</i> or <i>in-out</i> parameters. See Section 3.3.3, "Data conversion when calling Automation methods" for more details.</p>	
Example	<p>For example, in order to set the <code>width</code> property of an interface pointer in the variable <code>doc</code>:</p> <pre>(invoke-dispatch-put-property doc "Width" 10)</pre>	
See also	<pre>invoke-dispatch-method invoke-dispatch-get-property call-dispatch-put-property</pre>	

make-lisp-variant*Function*

Summary	Returns a Lisp object that contains a type and a value.
Package	<code>com</code>
Signature	<code>make-lisp-variant</code> <i>type</i> &optional <i>value</i> => <i>lisp-variant</i>
Description	<p>The function <code>make-lisp-variant</code> returns a <code>lisp-variant</code> object <i>lisp-variant</i> containing <i>type</i> and <i>value</i>.</p> <p><i>lisp-variant</i> can be passed as an argument to an Automation method, to give control over the VT code that the method sees. The meaning of <i>type</i> and <i>value</i> are as described for <code>set-variant</code>.</p>
See also	<code>lisp-variant</code> <code>set-variant</code>

:midl-type-library-file*Defsystem Member Type*

Summary	A defsystem member type that can be used to include a type library file in a Lisp system definition.
Package	<code>com</code>
Description	<p>When a file is given the type <code>:midl-type-library-file</code>, compiling the system will compile the type library file to produce a fasl. Loading the system will load this fasl. The <code>:package</code> and <code>:mapping-options</code> keywords can be specified as for <code>midl</code>.</p> <p>The keyword <code>:component-name</code> <i>name-spec</i> can be supplied to specify that the source is the library specified by <i>name-spec</i>. <i>name-spec</i> should be one of:</p>

t	Means that the component name is the same as the module name.
A string	The name of the component.
A list	(<i>component-name keywords-and-values</i>) where the keywords and values are passed to <code>find-component-tlb</code> when looking for the actual library.

In all cases the module name, less anything after the last dot, is used as the default filename for the compiled file.

The keyword `:com` can be supplied to reduce the amount of code generated. For the details, see “Reducing the size of the converted library” on page 90.

Examples

To include the file `myfile.tlb` in a system, use

```
(defsystem my-system ()
  :members (("myfile.tlb"
            :type :midl-type-library-file)))
```

To compile the library associated with "OWC10.Spreadsheet", producing an object file in `OWC10.ofas1` put a clause like this in the `defsystem` form:

```
("OWC10.SPREADSHEET" :type :midl-type-library-file
  :com :not-binary
  :component-name t)
```

To compile the same library, but to a different object file, use:

```
("my-owc" :type :midl-type-library-file
  :com :not-binary
  :component-name "OWC10.SPREADSHEET")
```

To compile the same library, but using only version newer than 1.1, use a clause like this:

```
("my-owc" :type :midl-type-library-file
  :com :not-binary
  :component-name ("OWC10.SPREADSHEET"
                  :min-version "1.1"))
```

See also `find-component-tlb`
`:midl-file`

print-i-dispatch-methods

Function

Summary Prints the defined methods for an `i-dispatch`.

Package `com`

Signature `print-i-dispatch-methods i-dispatch &optional arguments-p`

Arguments *i-dispatch* An `i-dispatch` interface object.
arguments-p A boolean.

Description The function `print-i-dispatch-methods` prints the methods that are defined for the `i-dispatch` *i-dispatch*.

`print-i-dispatch-methods` tries to get the information about the methods of the `i-dispatch` and print them in a readable format. If *arguments-p* is `nil` then for each each method it prints its name, followed by the invocation type(s) inside curly brackets. Invocation types are:

"Method" Invoked by `invoke-dispatch-method`.

"Get" Invoked by `invoke-dispatch-get-property`.

"Put", "Putref" Invoked by `invoke-dispatch-put-property`.

If *arguments-p* is true, `print-i-dispatch-methods` also prints the types of the arguments for each method. The type of each argument is shown as a plain string followed by the `VT_`*constant* name delimited by curly brackets. The type may be preceded by:

By reference Means the argument has `VT_BYREF`. The argument in that is passed in Lisp should be the actual type. By reference argument values are returned as multiple values, following the return value of the method if it has one.

Array of Means it got `VT_ARRAY`. The argument in Lisp should be an array.

Array of references
 Means it got `VT_ARRAY` and `VT_BYREF`. The argument needs to be an array of the actual type.

The default value of *arguments-p* is `nil`.

Notes

1. `print-i-dispatch-methods` gives only partial information, and is therefore useful only for the simple methods where it is pretty obvious what the arguments are. If the arguments are not obvious, you will need to read the actual documentation.
2. The type Variant means any type, but note that the method may accept only specific types even if the argument is variant.

See also

`get-i-dispatch-name`
`i-dispatch`
`invoke-dispatch-put-property`
`invoke-dispatch-get-property`
`invoke-dispatch-method`
“Calling Automation methods without a type library” on page 92

query-simple-i-dispatch-interface*Function*

Summary	Queries the interface pointer from a <code>simple-i-dispatch</code> object using the type information from another interface.	
Package	<code>com</code>	
Signature	<code>query-simple-i-dispatch-interface</code> <i>this</i> &key <i>related-dispatch</i> => <i>interface-ptr</i> , <i>refguid</i>	
Arguments	<i>this</i>	A <code>simple-i-dispatch</code> object.
	<i>related-dispatch</i>	An <code>i-dispatch</code> interface pointer.
Values	<i>interface-ptr</i>	An interface pointer.
	<i>refguid</i>	A <code>refguid</code> .
Description	<p>The function <code>query-simple-i-dispatch-interface</code> is used to obtain an interface pointer from a <code>simple-i-dispatch</code> interface. The <code>simple-i-dispatch</code> contains the interface name provided using its <code>:interface-name</code> initarg, but it does not have the details of this interface, so <code>query-simple-i-dispatch-interface</code> must be able to find the details.</p> <p>In the current implementation, the only way for the details to be found is by passing the <i>related-dispatch</i> argument. This should be an interface pointer from which type information about the interface name can be obtained.</p> <p>The <code>query-simple-i-dispatch-interface</code> function returns two values, <i>interface-ptr</i> which is an interface pointer for the interface-name contained in <i>this</i> and <i>refguid</i>, which is the <code>refguid</code> of that interface-name.</p> <p>A typical use of <code>query-simple-i-dispatch-interface</code> is to implement a sink interface for events from some other component. The interface pointer for that component is passed as the <i>related-dispatch</i> because that connects to the type library containing both interface definitions.</p>	

Before using `query-simple-i-dispatch-interface` directly, consider the functions `set-i-dispatch-event-handler` and `create-instance-with-events`, which provide an succinct way to provide an event callback.

See also `simple-i-dispatch`
`create-instance-with-events`
`set-i-dispatch-event-handler`

register-active-object

Function

Summary Registers an instance of a coclass.

Signature `register-active-object interface_ptr &key clsid progid flags => token`

Arguments *interface_ptr* A COM interface pointer.
clsid A string or a `refguid` giving a CLSID to create.
progid A string giving a ProgID to create.
flags An integer.

Values *token* An integer.

Description Registers *interface_ptr* in the system Running Object Table for a specific coclass that the application implements. The coclass can be specified directly by using the *clsid* argument or indirectly using the *progid* argument, which will locate the CLSID from the registry.

flags can be an integer as specified for the Win32 API function `RegisterActiveObject`. The default value of *flags* is 0.

The returned value *token* can be used with `revoke-active-object` to revoke the registration.

See also `revoke-active-object`

revoke-active-object

Function

Summary Unregisters a previously registered instance of a coclass.

Signature `revoke-active-object token`

Arguments *token* An integer.

Description Revokes the registration of the object associated with *token* in the system Running Object Table. The value of *token* should be one that was returned by a call to `register-active-object`.

See also `register-active-object`

set-error-info

Function

Summary Sets the error information for the current Automation method.

Package `com`

Signature `set-error-info &key iid source description help-file help-context => error-code`

Arguments *iid* The iid of the interface that defined the error, or `nil` if none. The iid can be a symbol naming the interface or a `refguid` foreign pointer.

source A string giving the ProgID for the class that raised the error, or `nil` if none.

	<i>description</i>	A string giving the textual description of the error, or <code>nil</code> if none.
	<i>help-file</i>	A string giving the path of the help file that describes the error, or <code>nil</code> if none.
	<i>help-context</i>	An integer giving the help context id for the error, or <code>nil</code> if none.
Values	<i>error-code</i>	The error code <code>DISP_E_EXCEPTION</code> or <code>nil</code> if the error info could not be set.

Description The function `set-error-info` allows the various components of the error information to be set for the current Automation method. It should only be called within the dynamic scope of the body of a `define-com-method` definition. The value `DISP_E_EXCEPTION` can be returned as the `hresult` of the method to indicate failure.

Examples

```
(define-com-method (i-robot rotate)
  ((this i-robot-impl)
   (axis :in)
   (angle-delta :in))
  (let ((joint (find-joint axis)))
    (if joint
      (progn
        (rotate-joint joint)
        S_OK)
      (set-error-info :iid 'i-robot
                     :description "Bad joint."))))
```

See also

```
define-com-method
get-error-info
refguid
hresult
```

set-i-dispatch-event-handler

Function

Summary Sets an event handler for an `i-dispatch` interface.

Package	com	
Signature	<code>set-i-dispatch-event-handler</code> (<i>interface event-handler</i> &key <i>all coclass event-object source-names</i>) => <i>sinks</i>	
Arguments	<i>interface</i>	An <code>i-dispatch</code> interface.
	<i>event-handler</i>	A function of four arguments.
	<i>all</i>	A generalized boolean, default value false.
	<i>coclass</i>	The coclass to use, or <code>nil</code> .
	<i>event-object</i>	A Lisp object.
	<i>source-names</i>	A list of "source" interface names, or <code>nil</code> .
Values	<i>sinks</i>	A list of objects representing the connections made.
Description	<p>The function <code>set-i-dispatch-event-handler</code> sets an event handler for the <code>i-dispatch</code> interface <i>interface</i>.</p> <p><i>event-handler</i> is a function of four arguments:</p> <p><code>event-handler event-obj method-name method-type args</code></p> <p><i>event-obj</i> is the value of <i>event-object</i> if this is non-<code>nil</code>. If <i>event-object</i> is <code>nil</code>, <i>event-obj</i> is the value of <i>interface</i>.</p> <p><i>method-name</i> is the method-name that has been called, which is the same as the "event" name in Visual Basic terminology.</p> <p><i>method-type</i> is the type of the method. For a normal "event" it is <code>:method</code>. <i>method-type</i> can also be <code>:put</code> or <code>:get</code> if the underlying "source" interface has "propput" or "propget" methods or properties.</p> <p><i>args</i> is an array containing the arguments to the method ("event"). This varies according to the method. For <i>out</i> or <i>in-out</i> arguments, it is possible to return a value by setting the corresponding value in the array.</p>	

The *all*, *coclass* and *source-names* arguments to `set-i-dispatch-event-handler` tell it which "source" interface or interfaces to use. In most cases, the default is correct.

If *all* is false, then only the "default" "source" is used. If *all* is true, then `set-i-dispatch-event-handler` uses all the source interfaces that the coclass defines.

coclass tells `set-i-dispatch-event-handler` which coclass to use, which is the same as the object in Visual Basic terminology.

If *coclass* is `nil`, it uses the first coclass in the type library that has the type of *interface* as a default interface, or if there is no such coclass, the first coclass that has this interface. In most of the cases this is the desired coclass.

If *coclass* is non-`nil`, it specifies which coclass to use. It can be a ProgID (for example "Word.Application") or a coclass name or a coclass GUID. If the *i-dispatch interface* was created with `create-instance`, then the argument to `create-instance` is the correct coclass to use.

If *source-names* is non-`nil`, then it is a list of "source" interface names to use, and *all* and *coclass* are ignored. If *source-names* is `nil`, then `set-i-dispatch-event-handler` calls `get-i-dispatch-source-names` to calculate the "source" interface names.

sinks is a list of objects representing the connections that `set-i-dispatch-event-handler` made. When the events are no longer needed, they can be released by `disconnect-standard-sink`.

Notes

1. `set-i-dispatch-event-handler` can be called more than once on the same *i-dispatch*, and this generates new connections each time. Therefore, if it is called more than once such that it uses the same source names, events will arrive more than once.

2. If you need to call `set-i-dispatch-event-handler` repeatedly, then it is most efficient to call `get-i-dispatch-source-names` once and pass the result *source-names* to `set-i-dispatch-event-handler`.
3. There is a useful function `create-instance-with-events` which combines `create-instance` and `set-i-dispatch-event-handler`.

See also `disconnect-standard-sink`
`create-instance-with-events`
`get-i-dispatch-source-names`

set-variant

Function

Summary Sets the fields in a `VARIANT` pointer.

Package `com`

Signature `set-variant variant type &optional value`

Arguments

<i>variant</i>	A foreign pointer to an object of type <code>VARIANT</code> .
<i>type</i>	A keyword specifying the type of value.
<i>value</i>	The value to store in <i>variant</i> .

Description The function `set-variant` can be used to set the type and value of a `VARIANT` object. It is useful if the default type provided by the automatic conversion for `VARIANT` return values is incorrect. The value of meaning of *type* is an specified below

Value of <i>type</i>	vt code used	Expected type of <i>value</i>
<code>nil</code>	<code>dynamic</code>	any suitable

Value of <i>type</i>	VT code used	Expected type of <i>value</i>
:empty	VT_EMPTY	ignored
:null	VT_NULL	ignored
:short	VT_I2	integer
:long	VT_I4	integer
:float	VT_R4	single-float
:double	VT_R8	double-float
:cy	VT_CY	
:date	VT_DATE	
:bstr	VT_BSTR	string
:dispatch	VT_DISPATCH	FLI pointer
:error	VT_ERROR	ignored
:bool	VT_BOOL	nil or non nil
:variant	VT_VARIANT	FLI pointer
:unknown	VT_UNKNOWN	FLI pointer
:decimal	VT_DECIMAL	
(:unsigned :char)	VT_UI1	integer
(:array . <i>type</i>)	VT_BYREF + VT code for <i>type</i>	array
:array or (:array <i>array</i>) or (:array . <i>types</i>)	VT_ARRAY + VT_VARIANT	array
(:pointer <i>type2</i>)	VT_BYREF + VT code for <i>type2</i>	FLI pointer

If *type* is `nil` then the actual VT code is chosen dynamically according to the Lisp type of *value* (see Table 3.1, page 93).

If *type* is a cons of the form `(:array . type)` for some keyword *type*, then *variant* is set to contain an array of objects of *type*. Each element of *value* is expected to be suitable for conversion to *type*.

If *type* is `:array` or another list starting with `:array` then *variant* is set to contain an array of `VARIANT` objects with the same dimensions as *value*. Each element of *value* is converted as if by calling `set-variant` with a type chosen as follows:

- If *type* is the symbol `:array`, then `nil` is passed as the element type.
- If *type* is of the form `(:array array)` then *array* should be an array with the same dimensions as *value*. The element type is taken from the corresponding element of *array*.
- If *type* is of the form `(:array . types)` then *types* should be a suitable value for the `:initial-contents` argument to `make-array` to make an array of types with the same dimensions as *value*. The element type is taken from the corresponding element of that array. In particular, if *value* is a vector of length *n* then *type* should be a list of the form `(:array type1 type2 ... typen)`.

Examples

```
(set-variant v :null)
(set-variant v :short 10)
(set-variant v '(:pointer :short) ptr)
(set-variant v '(:array :short :int) #(1 2))
```

See also

`define-com-method`

simple-i-dispatch

Class

Summary

A complete dynamic implementation of the `i-dispatch` interface.

Package

`com`

Superclasses

`standard-i-dispatch`

Subclasses

None

Initargs	<p><code>:interface-name</code></p> <p>The name of the interface to implement. See <code>query-simple-i-dispatch-interface</code> for details on how this is used.</p> <p><code>:invoke-callback</code></p> <p>A function that is called with four arguments whenever one of the interface's methods is invoked. The arguments are the callback object, the method name as a string, the method type (a keyword <code>:method</code>, <code>:get</code> or <code>:put</code>) and a vector of the method's arguments. The value returned by the function will be returned to the caller of the method. See <code>com-object-dispinterface-invoke</code> for more details of the method name, type and arguments.</p>
Accessors	<code>simple-i-dispatch-invoke-callback</code>
Readers	<code>simple-i-dispatch-interface-name</code> <code>simple-i-dispatch-refguid</code>
Description	<p>The class <code>simple-i-dispatch</code> provides a complete implementation of the <code>i-dispatch</code> interface, without requiring a type library to be parsed. The type information is obtained at run-time when <code>query-simple-i-dispatch-interface</code> is called. The class inherits from <code>standard-i-dispatch</code> to provide the <code>i-unknown</code> interface.</p> <p>The <code>simple-i-dispatch-refguid</code> reader can be used to return the <code>refguid</code> of the interface. This can only be called after <code>query-simple-i-dispatch-interface</code> has been called.</p> <p>The implementation obtains the callback object argument to the <code>invoke-callback</code> by calling <code>simple-i-dispatch-callback-object</code> with the <code>simple-i-dispatch</code> object. The default method returns the <code>simple-i-dispatch</code> object itself,</p>

but this method can be overridden for subclasses to return some other object.

Before using `simple-i-dispatch` directly, consider the functions `set-i-dispatch-event-handler` and `create-instance-with-events`, which provide an succinct way to provide an event callback.

See also `query-simple-i-dispatch-interface`
`simple-i-dispatch-callback-object`
`standard-i-dispatch`
`i-dispatch`
`capi:ole-control-pane-simple-sink`

simple-i-dispatch-callback-object

Generic Function

Summary A generic function that can be implemented to modify the first argument to the *invoke-callback* in `simple-i-dispatch`.

Package `com`

Signature *this* => *object*

Method signature (*this* `simple-i-dispatch`) => *this*

Arguments *this* An object of type `simple-i-dispatch`.

Values *object* The callback object to be pass as the first argument to the *invoke-callback* of *this*.

Description The generic function `simple-i-dispatch-callback-object` is called by the implementation of `simple-i-dispatch` to obtain the callback object (first argument) to its *invoke-callback*. This allows the object to be computed in some way by subclassing `simple-i-dispatch` and implementing

a method on `simple-i-dispatch-callback-object` specialized for the subclass.

The pre-defined primary method specializing on `simple-i-dispatch` always returns its argument.

Example

When the function `my-dispatch-callback` below is called, its first argument will be the *useful-object* passed to `make-my-dispatch`.

```
(defclass my-dispatch (simple-i-dispatch)
  ((useful-object :initarg :useful-object)))

(defmethod simple-i-dispatch-callback-object
  ((this my-dispatch))
  (slot-value this 'useful-object))

(defun make-my-dispatch (useful-object)
  (make-instance
   'my-dispatch
   :useful-object useful-object
   :invoke-callback 'my-dispatch-callback
   :interface-name "MyDispatchInterface"))
```

See also `simple-i-dispatch`

standard-automation-collection

Class

Summary A framework for implementing Automation collections.

Package `com`

Superclasses `standard-i-dispatch`

Initargs `:count-function`

A function of no arguments that should return the number of items in the collection. This initarg is required.

`:items-function`

A function of no arguments that should return a sequence of items in the collection. This function is called by the implementation of `_NewEnum` and the sequence is copied. Exactly one of `:items-function` and `:item-generator-function` must be specified.

`:item-generator-function`

A function of no arguments that should return an *item generator*, which will generate the items in the collection. See below for more details. Exactly one of `:items-function` and `:item-generator-function` must be specified.

`:data-function`

A function called on each item that the `:items-function` OR `:item-generator-function` returns. This is called when iterating, to produce the value that is returned to the caller.

`:item-lookup-function`

A function which takes a single argument, an integer or a string specifying an item. The function should return the item specified. This initarg is required if the `:item-method` option is non-nil in `define-automation-collection`.

Description

The class `standard-automation-collection` provides a framework for implementing Automation collections. These typically provide a `Count` property giving the number of objects in the collect, a `_NewEnum` property for iterating over the element of the collection method and optionally an `Item` method for finding items by index or name.

The `:count-function` initarg specifies a function to count the items of the collection and is invoked by the implementation of the `Count` method.

Exactly one of the initargs `:item-function` and `:item-generator-function` must be specified to provide items for the implementation of the `IEnumVARIANT` instance returned by the `_NewEnum` method.

If `:items-function` is specified, then it will be called once when `_NewEnum` is called and should return a sequence of the items in the collection. This sequence is copied, so can be modified by the program without affecting the collection.

If `:item-generator-function` is specified, it should be an *item generator* that will generate all the items in the collection. It will be called once with the argument `:clone` when `_NewEnum` is called and then by the implementation of the resulting `IEnumVARIANT` interface. An *item generator* is a function of one argument which specifies what to do:

<code>:next</code>	Return two values: the next item and <code>t</code> . If there are no more items, return <code>nil</code> and <code>nil</code> .
<code>:skip</code>	If there are no more items, return <code>nil</code> . Otherwise skip the current item and return <code>t</code> .
<code>:reset</code>	Reset the generator so the first item will be returned again.
<code>:clone</code>	Return a copy of the <i>item generator</i> . The copy should have the same current item.

The `:data-function` initarg should be function to convert each item returned by the `:items-function` or the item generator into a value whose type is compatible with Automation (see Table 3.1, page 93). The default function is `identity`.

Example See the example in this directory:

```
(example-edit-file "com/automation/collections/")
```

See also `define-automation-collection`
`standard-i-dispatch`
`i-dispatch`

standard-i-connection-point-container

Class

Summary A complete implementation of the Connection Point protocol.

Package `com`

Superclasses `standard-i-unknown`

Description The class `standard-i-connection-point-container` provides a complete implementation of the Connection Point protocols. It implements the `IConnectionPointContainer` interface and creates connection points for each interface given by the `:outgoing-interfaces` initarg.

If a class defined with `define-automation-component` macro specifies the `:source-interfaces` option or has interfaces with the "source" attribute in its coclass then it must inherit from `standard-i-connection-point-container` somehow. `define-automation-component` passes the appropriate initargs to initialize the class.

The macro `do-connections` can be used to iterate over the connections (sinks) for a given interface.

Example Given the class definition

```
(define-automation-component clonable-component ()
  ()
  (:interfaces i-clonable)
  (:source-interfaces i-clonable-events)
)
```

then

```
(typep (make-instance 'clonable-component)
       'standard-i-connection-point-container)
=> t
```

See also

- `define-automation-component`
- `standard-i-dispatch`
- `do-connections`
- `define-automation-collection`
- `standard-i-unknown`
- `i-dispatch`

standard-i-dispatch

Class

Summary A complete implementation of the `i-dispatch` interface.

Package `com`

Superclasses `standard-i-unknown`

Subclasses `standard-automation-collection`
`simple-i-dispatch`

Description The class `standard-i-dispatch` provides a complete implementation of the `i-dispatch` interface, based on the type information in the type library. In addition, the `i-support-error-info` interface is implemented to support error information. `standard-i-dispatch` inherits from `standard-i-unknown` to provide the `i-unknown` interface.

All classes defined with the `define-automation-component` and `define-automation-collection` macros must inherit from `standard-i-dispatch` somehow. These macros pass the appropriate `initargs` to initialize the class.

Example Given the class definition

```
(define-automation-component document-impl ()
  ()
  (:coclass document)
  )

then

(typep (make-instance 'document-impl)
  'standard-i-dispatch)
=> t
```

See also

```
define-automation-component
define-automation-collection
standard-i-connection-point-container
standard-i-unknown
i-dispatch
```

with-coclass*Macro*

Summary	Executes a body of code with a temporary instance of a coclass.	
Package	com	
Signature	<code>with-coclass <i>disp form*</i> => <i>values</i></code> <code><i>disp ::= (dispatch-function coclass-name &key interface-name punk clctx)</i></code>	
Arguments	<i>disp</i>	The names of the dispatch function, coclass and so on.
	<i>dispatch-function</i>	A symbol which will be defined as a macro, as if by <code>with-dispatch-interface</code> . The macro can be used by the <i>forms</i> to invoke the Automation methods of the component.
	<i>coclass-name</i>	A symbol which names the coclass. It is not evaluated.

	<i>interface-name</i>	A symbol naming an interface in the coclass. It is not evaluated.
	<i>punk</i>	A symbol which will be bound to the interface pointer.
	<i>clsctx</i>	A CLSCTX value, which defaults to <code>CLSCTX_SERVER</code> .
	<i>form</i>	A form to be evaluated.
Values	<i>values</i>	The values returned by the last <i>form</i> .
Description		Calls <code>create-object</code> to make an instance of the coclass named by the symbol <i>coclass-name</i> . If <i>interface-name</i> is given then that interface is queried from the component, otherwise the default interface is queried. Each <i>form</i> is evaluated in turn with <i>dispatch-function</i> bound of a local macro for invoking methods on the interface, as if by <code>with-dispatch-interface</code> . After the forms have been evaluated, the interface pointer is released. If <i>punk</i> is given, it will be bound to the interface pointer while the forms are being evaluated.
Example		If a type library containing the coclass <code>TestComponent</code> has been converted to Lisp, then following can be used to make an instance of component and invoke the <code>Greet ()</code> method on the default interface. <pre>(with-coclass (call-it test-component) (call-it greet "hello"))</pre>
See also	<code>create-object</code>	

with-dispatch-interface

Macro

Summary	Used to simplify invocation of several methods from a particular Automation interface pointer.
---------	--

Package	<code>com</code>
Signature	<code>with-dispatch-interface <i>disp</i> <i>dispinterface-ptr</i> <i>form</i>* => <i>values</i></code> <code><i>disp</i> ::= (<i>dispatch-function</i> <i>dispinterface-name</i>)</code>
Arguments	<p><i>disp</i> The names of the dispatch function and Automation interface.</p> <p><i>dispatch-function</i> A symbol which will be defined as a macro, as if by <code>macrolet</code>. The macro can be used by the <i>forms</i> to invoke the methods on <i>dispinterface-ptr</i>.</p> <p><i>dispinterface-name</i> A symbol which names the Automation interface. It is not evaluated.</p> <p><i>dispinterface-ptr</i> A form which is evaluated to yield a <code>COM i-dispatch</code> interface pointer.</p> <p><i>form</i> A form to be evaluated.</p>
Values	<i>values</i> The values returned by the last <i>form</i> .
Description	<p>When the macro <code>with-dispatch-interface</code> evaluates the <i>forms</i>, the local macro <i>dispatch-function</i> can be used to invoked the methods for the Automation interface <i>dispinterface-name</i>, which should be the type or a supertype of the actual type of the Automation interface pointer <i>dispinterface-ptr</i>.</p> <p>The <i>dispatch-function</i> macro has the following signature:</p> <p><code><i>dispatch-function</i> <i>method-name</i> <i>arg</i>* => <i>values</i></code></p> <p>where</p> <p><i>method-name</i> A symbol which names the method. It is not evaluated.</p>

arg Arguments to the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).

values Values from the method (see Section 3.3.3, “Data conversion when calling Automation methods” for details).

Example For example, in order to invoke the `ReFormat` method of a `MyDocument` interface pointer

```
(with-dispatch-interface (call-doc my-document) doc
 (call-doc re-format))
```

See also `call-dispatch-method`

5


Tools

The tools described in this chapter extend the LispWorks IDE to help with debugging applications using COM/Automation. See the *LispWorks IDE User Guide* for more details of common operations that can be performed within these tools. The sections below describe each tool.

5.1 The COM Implementation Browser

The COM Implementation Browser allows prototype code for COM implementation classes to be viewed and created. This is useful when writing COM methods because it provides a template for the method names and arguments.

To start the tool, choose **Tools > Com Implementation Browser** from the Lisp-Works podium.




At the top of the window is a drop down list a class names. Choosing an item from this list will set the contents of the Description panel to show that class at the root of the tree, with subitems for each COM interface that it implements. The COM interfaces have subitems for their uuids and methods. The icon used for a method in the tree indicates the status of its implementation: red means not implemented (see Section 1.8.4 on page 17), yellow means inherited from a superclass (see Section 1.8.5 on page 17), red and yellow means an inherited unimplemented method and cyan means a method implemented directly in the named class.

Selecting an item in the Description pane will display a prototype implementation for that part of the class, using the appropriate macros for COM and Automation classes.

The **New** and **Edit** buttons allow prototype classes to be constructed and modified. Such classes are shown in the list of class names as **Example class...** and are not actually defined, but the prototype code can be copied into a file and


evaluated to provide a starting point for an implementation. Clicking **New** or **Edit** displays a dialog as shown below.



The class name is displayed at the top and can be edited. For COM object classes, the list at the bottom of the dialog shows the COM interfaces that the class will implement. For Automation interfaces, a type library must be chosen from the drop-down list and one of the **Coclass** or **Interfaces** options selected to show the list of coclasses or interfaces that the class will implement. Click **OK** to confirm your choice or **Cancel** to discard it.

5.2 The COM Object Browser


The COM Object Browser is used view COM objects for the classes implemented by Lisp. To start the tool, choose **Tools > Com Object Browser** from the LispWorks podium.



The **Active COM Objects** list shows all the Lisp objects that are known to the COM runtime system. Selecting objects from this list will list the COM interface pointers that have been queried for these objects. Double clicking on either list will inspect the data. Use the **Works > Object** menu or the context menu to perform other operations on the selected COM Objects.

5.3 The COM Interface Browser

The COM Interface Browser allows the interfaces that have been converted to FLI definitions to be viewed. To start the tool, choose **Tools > Com Interface Browser** from the LispWorks podium.



Interfaces and methods

Prototype code for invoking methods

The left hand pane shows a tree of the interfaces, with subitems for their uuids and methods. Selecting an item will cause the right-hand pane to show prototype code for invoking the method(s) selected.

5.4 Editor extensions

The LispWorks editor has been enhanced to support COM.

5.4.1 Inserting GUIDs

The editor command `Insert GUID` can be used to insert a new GUID at the current point. The GUID is made by calling `CoCreateGUID`.

5.4.2 Argument lists

The editor command `Function Arglist (Alt+=)` has been extended to show the arguments for all COM methods which match the function name.

6

Self-contained examples

This chapter enumerates the set of examples in the LispWorks library relevant to the content of this manual. Each example file contains complete, self-contained code and detailed comments, which include one or more entry points near the start of the file which you can run to start the program.

To run the example code:

1. Open the file in the Editor tool in the LispWorks IDE. Evaluating the call to `example-edit-file` shown below will achieve this.
2. In some cases you can simply compile the example code, by `Ctrl+Shift+B`, and then place the cursor at the end of the entry point form and press `Ctrl+X Ctrl+E` to run it. However the comments near the start of the file may have specific instructions, such as how to build a delivered executable or library, so follow these if present.

6.1 Argument passing

These files comprise an example illustrating various argument passing issues when calling and implementing COM methods. To run the example, follow the instructions in `defsys.lisp`.

```
(example-edit-file "com/manual/args/defsys")
```

```
(example-edit-file "com/manual/args/args.idl")
```

```
(example-edit-file "com/manual/args/args-impl")  
(example-edit-file "com/manual/args/args-calling")
```

6.2 Aggregation

These three files contain a simple demonstration of implementing aggregation:

```
(example-edit-file "com/com/aggregation-defsys")  
(example-edit-file "com/com/aggregation-idl.idl")  
(example-edit-file "com/com/aggregation")
```

6.3 OLE embedding of external components

These examples illustrate OLE embedding of external components in a CAPI interface:

```
(example-edit-file "com/ole/html-viewer")  
(example-edit-file "com/ole/flash-player")  
(example-edit-file "com/ole/simple-container/doc-viewer-pair")
```

These three files together comprise an example also illustrating OLE embedding: Start by loading the first file:

```
(example-edit-file  
  "com/ole/simple-container/do-simple-spreadsheet")  
(example-edit-file "com/ole/simple-container/defsys")  
(example-edit-file "com/ole/simple-container/owc-spreadsheet")
```

6.4 Building an ActiveX control

These three files together comprise an example which illustrates building an ActiveX control. Start by reading the comments in the first file:

```
(example-edit-file "com/ole/control-implementation/deliver")  
(example-edit-file "com/ole/control-implementation/defsys")
```

```
(example-edit-file
 "com/ole/control-implementation/my-control-implementation")
```

This file shows how you can embed the new ActiveX control in another application:

```
(example-edit-file
 "com/ole/control-implementation/lisp-container")
```

6.5 OLE automation

These examples illustrate using OLE automation:

```
(example-edit-file "com/automation/internet-explorer/simple")
(example-edit-file "com/automation/excel/pie-chart")
```

This is a simple example of an Automation collection interface. Follow the instructions in `defsys.lisp`:

```
(example-edit-file "com/automation/collections/defsys")
(example-edit-file
 "com/automation/collections/collection-test.idl")
(example-edit-file "com/automation/collections/client")
(example-edit-file "com/automation/collections/server")
(example-edit-file "com/automation/collections/compile.tlb")
```

This is an example of building and testing a CAPI application that can be controlled by Automation. Start with `readme.txt`:

```
(example-edit-file "com/automation/capi-application/readme.txt")
(example-edit-file "com/automation/capi-application/build")
(example-edit-file "com/automation/capi-application/defsys")
(example-edit-file "com/automation/capi-application/listapp.idl")
(example-edit-file "com/automation/capi-application/listapp.tlb")
(example-edit-file "com/automation/capi-application/automation")
(example-edit-file "com/automation/capi-application/application")
(example-edit-file "com/automation/capi-application/test")
```

These two files illustrate use of the CrystalDesignRunTime component:

```
(example-edit-file "com/automation/crystal-reports/deliver")
```

```
(example-edit-file "com/automation/crystal-reports/abrowse")
```

This example illustrates using events with Internet Explorer:

```
(example-edit-file "com/automation/events/ie-events")
```

This is an example of building an Automation server without a GUI.

```
(example-edit-file "com/automation/cl-smtp/clsmtpl-build")
```

```
(example-edit-file "com/automation/cl-smtp/clsmtpl.idl")
```

```
(example-edit-file "com/automation/cl-smtp/clsmtpl.tlb")
```

```
(example-edit-file "com/automation/cl-smtp/clsmtpl-impl")
```

```
(example-edit-file "com/automation/cl-smtp/server")
```

```
(example-edit-file "com/automation/cl-smtp/clsmtpl-test")
```

Index

A

accessor functions
 lisp-variant-type 131
 lisp-variant-value 131
ActiveX controls vii
add-ref function 4, 27
automation-server-command-line-action function 28
automation-server-main function 29
automation-server-top-loop function 32

C

call-com-interface macro 4, 33
call-com-object macro 15, 24, 35
call-dispatch-get-property macro 103
call-dispatch-method macro 104
call-dispatch-put-property macro 106
Calling
 Automation methods
 using a type library 91
 without using a type library 92
 COM interface methods 4
 COM object methods 24
check-hresult macro 36
class options
 :coclass 114

:coclass-reusable-p 115
 :dont-implement 50
 :extra-interfaces 115
 :inherit-from 49
 :interface 112
 :interfaces 49, 114
 :item-method 112
 :source-interfaces 115
classes
 com-dispatch-invoke-exception-error 101
 com-error 41
 com-interface 42
 com-object 43
 simple-i-dispatch 148
 standard-automation-collection 151
 standard-i-connection-point-container 154
 standard-i-dispatch 155
 standard-i-unknown 77
 :coclass class option 114
 :coclass-reusable-p class option 115
co-create-guid function 37
co-initialize function 14, 38
collections
 implementing 97
 using 94
COM interface types
 i-dispatch 128
 i-unknown 57
com-dispatch-invoke-exception-error class 101
com-dispatch-invoke-exception-error-info function

102
com-error class 41
com-error-function-name function 41
com-error-hresult function 41
com-interface class 4, 42, 92, 93
com-interface-refguid function 42
com-object class 43
com-object-destroyer function 16, 43
**com-object-dispinterface-
 invoke** generic function 107
com-object-from-pointer function 44
com-object-initialize function 16, 45
com-object-query-interface function 46
 compiling IDL files 1
 connection points
 implementing 98
 using 94
CoTaskMemAlloc 39
co-task-mem-alloc function 10, 38
CoTaskMemFree 40
co-task-mem-free function 8, 10, 40
co-uninitialize function 40
:count-function initarg 151
create-instance function 47
create-instance-with-events function 109
create-object function 110

D
:data-function initarg 152
define-automation-collection macro 111
define-automation-component macro 113
define-com-implementation macro 14, 48
define-com-method macro 14, 51
define-dispinterface-method macro 116
 defsystem member types
 :midl-file 65
 :midl-type-library-file 136
deliver function 2, 31, 33
 destruction 16
discard-connection function 121
disconnect-standard-sink func-

tion 118
 dispinterface 90, 96, 97, 103, 105, 106, 107, 116, 158
:dll-exports Delivery keyword 2, 76
do-collection-items macro 119
do-connections macro 120
:dont-implement class option 50
 dual interface 90, 96

E

editor commands
 Function Arglist 167
 Insert GUID 167
 environment variables
 INCLUDE 62, 65
 errors
 handling in Automation 95
 handling in COM 12
 reporting 98
 events
 see connection-points
:extra-interfaces class option 115

F

find-clsid function 53
find-component-tlb function 122
find-component-value function 123
 FLI types
 hresult 56
 refguid 68
 refiid 69
Function Arglist editor command 167
:function-name initarg 41
 functions
 add-ref 27
 automation-server-command-line-action 28
 automation-server-main 29
 automation-server-top-loop 32
 co-create-guid 37
 co-initialize 14, 38
 com-dispatch-invoke-exception-error-info 102
 com-error-function-name 41
 com-error-hresult 41
 com-interface-refguid 42
 com-object-destroyer 16, 43
 com-object-from-pointer 44
 com-object-initialize 16, 45

com-object-query-interface
 46
co-task-mem-alloc 10, 38
co-task-mem-free 8, 10, 40
co-uninitialize 40
create-instance 47
create-instance-with-events
 109
create-object 110
discard-connection 121
disconnect-standard-sink 118
find-clsid 53
find-component-tlb 122
find-component-value 123
get-error-info 125
get-i-dispatch-name 126
get-i-dispatch-source-names
 127
get-object 54
guid-equal 55
guid-to-string 56
hresult-equal 57
interface-connect 129, 130
invoke-dispatch-get-property
 131
invoke-dispatch-method 133
invoke-dispatch-put-property
 134
make-factory-entry 14, 16, 59
make-guid-from-string 60
make-lisp-variant 136
midl 2, 61
midl-default-import-paths 64
midl-set-import-paths 65
print-i-dispatch-methods 138
query-interface 66
query-simple-i-dispatch-
interface 140
refguid-interface-name 69
register-class-factory-
entry 14, 16, 70
register-server 71
release 72
server-can-exit-p 74
server-in-use-p 74
set-automation-server-exit-
delay 75
set-error-info 142
set-i-dispatch-event-han-
dler 143
set-register-server-error-
reporter 75

set-variant 146
start-factories 14, 16, 78, 79
unregister-server 80

G

Garbage collection 16
generic functions
com-object-dispinterface-
invoke 107
simple-i-dispatch-callback-
object 150
get-error-info function 12, 125
get-i-dispatch-name function 126
get-i-dispatch-source-names
 function 127
get-object function 54
guid-equal function 55
guid-to-string function 56

H

hresult FLI type 56
:hresult initarg 41
hresult-equal function 57

I

i-dispatch COM interface type 128
IDL
 compiling 1
iid_is attribute 8
 in parameters 6, 21, 24, 93
INCLUDE environment variable 62, 65
:inherit-from class option 49
initialization
 CLOS object 15
 COM object 15
in-out parameters 10, 23, 25, 93
Insert GUID editor command 167
:interface class option 112
interface-connect function 129,
 130
:interface-name initarg 149
interface-ref macro 58
:interfaces class option 49, 114
:invoke-callback initarg 149
invoke-dispatch-get-property
 function 131
invoke-dispatch-method function
 133
invoke-dispatch-put-property
 function 134
:item-generator-function ini-

targ 152
:item-lookup-function initarg 152
:item-method class option 112
:items-function initarg 151
i-unknown COM interface type 57

L

lisp-variant type 131
lisp-variant-type accessor function 131
lisp-variant-value accessor function 131

M

macros
 call-com-interface 33
 call-com-object 15, 35
 call-dispatch-get-property 103
 call-dispatch-method 104
 call-dispatch-put-property 106
 check-hresult 36
 define-automation-collection 111
 define-automation-component 113
 define-com-implementation 14, 48
 define-com-method 14, 51
 define-dispinterface-method 116
 do-collection-items 119
 do-connections 120
 interface-ref 58
 query-object-interface 15, 67
 s_ok 73
 succeeded 79
 with-coclass 156
 with-com-interface 81
 with-com-object 83
 with-dispatch-interface 157
 with-query-interface 86
 with-temp-interface 85
make-factory-entry function 14, 16, 59
make-guid-from-string function 60
make-lisp-variant function 136
 making a COM DLL 2
midl function 2, 61

midl.exe 2, 5, 20
midl-default-import-paths function 64
:midl-file defsystem member type 65
midl-set-import-paths function 65
:midl-type-library-file defsystem member type 136

modules

automation 89
com 1, 89

N

name mapping 3
 New in LispWorks 7.0
 midl-default-import-paths function 64
 midl-set-import-paths function 65
 Optional Automation parameters can be passed as **:not-specified** 94
 print-i-dispatch-methods function 138
 Search paths for IDL import statements 63
 set-register-server-error-reporter function 75
 Newly documented in LispWorks 7.0
 :type-library class option for **define-automation-component** 116

O

OLE vii
 other applications
 registering objects for 98
 out parameters 7, 22, 25, 93
:outer-unknown initarg 77

P

parameter direction
 in 6, 21, 24, 93
 in-out 10, 23, 25, 93
 out 7, 22, 25, 93
 Primitive types 5, 20
print-i-dispatch-methods function 138
propget attribute 3
propput attribute 3
propputref attribute 3

Q

query-interface function 4, 66
query-object-interface macro 15, 67
query-simple-i-dispatch-interface function 140
:quit-when-no-windows Delivery keyword 33

R

refguid FLI type 68
refguid-interface-name function 69
refiid FLI type 4, 69
register-class-factory-entry function 14, 16, 70
register-server function 71
registry
 component values 123
 guid 53
 ProgID 53
 type library versions 122
release function 4, 72
retval attribute 93

S

s_ok macro 73
save-image function 2, 31
Self-contained examples
 ActiveX controls 170
 aggregation 170
 argument passing 169
 Automation 99
 calling and implementing COM methods 169
 COM/Automation 169, 170
 Controlling an Automation application 99
 embedding external components 170
 event handlers 172
 events 172
 Getting events from COM interfaces 99
 OLE automation 171
 OLE embedding 170
server-can-exit-p function 74
server-in-use-p function 74
set-automation-server-exit-delay function 75
set-error-info function 53, 98, 142
set-i-dispatch-event-handler function 143

set-register-server-error-reporter function 75
set-variant function 146
simple-i-dispatch class 148
simple-i-dispatch-callback-object generic function 150
size_is attribute 6, 8, 10, 21, 22, 23, 24, 25
source attribute 115
source interfaces 98
:source-interfaces class option 115
standard-automation-collection class 151
standard-i-connection-point-container class 154
standard-i-dispatch class 155
standard-i-unknown class 77
start-factories function 14, 16, 78, 79
string attribute 6, 7, 10, 21, 22, 23, 24, 25
succeeded macro 79

T

tools
 COM Implementation Browser 161
 COM Interface Browser 166
 COM Object Browser 165
type libraries 89
types
 lisp-variant 131

U

unregister-server function 80

W

Windows registry 53, 122, 123
with-coclass macro 156
with-com-interface macro 4, 81
with-com-object macro 24, 83
with-dispatch-interface macro 157
with-query-interface macro 4, 86
with-temp-interface macro 4, 85

